



HALCON

a product of MVTec

Extension Package Programmer's Manual



HALCON 23.11 *Progress*

This manual shows how to create HALCON extension packages based on new operators written in C, Version 23.11.0.0.

All rights reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without prior written permission of the publisher.

Copyright © 1997-2023 by MVTec Software GmbH, Munich, Germany



Protected by the following patents: US 7,239,929, US 7,751,625, US 7,953,290, US 7,953,291, US 8,260,059, US 8,379,014, US 8,830,229, US 11,328,478. Further patents pending.

Microsoft, Windows, Windows 10 (x64 editions), 11, Windows Server 2016, 2019, 2022 Microsoft .NET, Visual C++ and Visual Basic are either trademarks or registered trademarks of Microsoft Corporation.

Linux is a trademark of Linus Torvalds.

OpenCL is a trademark of Apple Inc.

Sun is a trademark of Oracle Corporation.

OpenGL is a trademark of Silicon Graphics, Inc.

All other nationally and internationally recognized trademarks and tradenames are hereby recognized.

More information about HALCON can be found at: <http://www.halcon.com>

About This Manual

This manual describes how to extend HALCON by additional operators encapsulated in HALCON packages using the Extension Package Interface. Before starting to use the Extension Package Interface, MVTec strongly recommends that the user should be familiar with the normal HALCON system.

This manual is written for the expert HALCON user who wants to extend the system for specific requirements. Thus, the reader should be familiar with the normal HALCON system. Furthermore, programming skills are required. Finally, the reader should know about his/her development environment (that is how to invoke the compiler/linker etc.).

This manual is divided into the following parts:

- **Introduction**
This chapter provides a short overview of HALCON packages and their creation. Furthermore, an example showing the integration of a simple operator is presented.
- **Operator Description (DEF file)**
This chapter summarizes the minimum required operator description used by the HALCON compiler `hcomp` as well as the complete operator description which is needed to provide a full integration of new operators in HDevelop and to generate documentation files.
- **Style Guide for Programming**
This chapter introduces basic style guides for how to program HALCON operators. Especially, the HALCON memory management is explained.
- **HALCON Data Types**
In this chapter the most important HALCON data structures to handle iconic data and control parameters are presented.
- **Handling Iconic Objects and Control Parameters**
This chapters contains a set of routines to facilitate the programming of the operator interface and accessing the basic HALCON data structures.
- **Special Routines for Typical Supply Procedures**
This chapter describes a set of convenience routines for standard situations.
- **Creating a New HALCON Package**
The last chapter explains how to use the HALCON compiler `hcomp` to generate HALCON packages for different platforms.

Symbols

The following symbol is used within the manual:



This symbol indicates an information you should **pay attention** to.

Contents

| | | |
|----------|--|-----------|
| 1 | Introduction | 9 |
| 1.1 | HALCON Operators | 9 |
| 1.1.1 | Using HALCON Operators in C, C++, and .NET Languages | 10 |
| 1.1.2 | Internal Structure of HALCON Operators | 10 |
| 1.2 | HALCON Packages | 11 |
| 1.2.1 | Packages and HALCON XL | 12 |
| 1.2.2 | Directory Structure of a HALCON Package | 12 |
| 1.2.3 | How to Create and Use a HALCON Package | 13 |
| 1.3 | Installing a HALCON Package | 13 |
| 1.3.1 | Windows | 14 |
| 1.3.2 | Linux | 14 |
| 1.4 | An Example | 14 |
| 2 | Operator Description (DEF File) | 19 |
| 2.1 | Short Operator Description | 19 |
| 2.2 | Extended Operator Description | 20 |
| 2.2.1 | Header | 20 |
| 2.2.2 | short | 21 |
| 2.2.3 | warning | 21 |
| 2.2.4 | abstract | 21 |
| 2.2.5 | module | 22 |
| 2.2.6 | chapter | 22 |
| 2.2.7 | functionality | 23 |
| 2.2.8 | keywords | 23 |
| 2.2.9 | predecessor, successor, alternatives | 23 |
| 2.2.10 | see_also | 23 |
| 2.2.11 | attention | 23 |
| 2.2.12 | result_state | 24 |
| 2.2.13 | parallelization | 24 |
| 2.2.14 | complexity | 27 |
| 2.2.15 | example | 27 |
| 2.2.16 | references | 27 |
| 2.2.17 | class Information | 27 |
| 2.3 | Describing the Parameters | 28 |
| 2.3.1 | Name | 28 |
| 2.3.2 | default_type | 29 |
| 2.3.3 | sem_type | 29 |
| 2.3.4 | modified | 30 |
| 2.3.5 | multivalue | 30 |
| 2.3.6 | costs_weight | 31 |
| 2.3.7 | postprocessing | 31 |
| 2.3.8 | description | 32 |
| 2.3.9 | type_list | 32 |
| 2.3.10 | default_value | 32 |
| 2.3.11 | values | 33 |
| 2.3.12 | value_list | 33 |
| 2.3.13 | value_min, value_max | 33 |

| | | |
|----------|---|-----------|
| 2.3.14 | step_rec, step_min, value_function | 33 |
| 2.3.15 | value_number | 33 |
| 2.3.16 | assertion | 34 |
| 2.3.17 | multichannel | 34 |
| 2.3.18 | multiinstance | 35 |
| 2.3.19 | file_ext, file_ext_descr | 35 |
| 2.4 | Text in DEF Files | 35 |
| 2.5 | Chapter Description | 38 |
| 3 | Style Guide for Programming | 39 |
| 3.1 | Basic Numeric Data Types | 39 |
| 3.1.1 | Attributes of Iconic Parameters | 39 |
| 3.1.2 | Local Variables / Temporary Results | 40 |
| 3.1.3 | Procedure Parameters | 40 |
| 3.1.4 | Arrays | 40 |
| 3.2 | Memory Management | 41 |
| 3.2.1 | Temporary Data | 41 |
| 3.2.2 | Permanent Data | 43 |
| 3.2.3 | Debugging | 45 |
| 3.3 | Structuring Programs | 46 |
| 3.4 | Extension Package Initialization | 46 |
| 3.5 | Name Conventions for Procedures | 46 |
| 3.6 | Input / Output | 47 |
| 3.7 | Error Handling | 47 |
| 3.7.1 | Defining Own Error Codes | 47 |
| 3.7.2 | Extending Error Codes | 47 |
| 3.8 | Notes on Image Processing Operators | 48 |
| 4 | HALCON Data Types | 49 |
| 4.1 | Pixel Data (Himage) | 49 |
| 4.2 | Region Data (Hregion) | 50 |
| 4.3 | XLDs (Hcont, Hpoly) | 52 |
| 4.4 | Control Parameters | 55 |
| 5 | Handling Iconic Objects and Control Parameters | 57 |
| 5.1 | Basic Access to Iconic Input Objects | 57 |
| 5.1.1 | HGetObj | 57 |
| 5.1.2 | HGetComp | 59 |
| 5.1.3 | HGetRL | 60 |
| 5.1.4 | HGetImage | 61 |
| 5.1.5 | HGetXLD | 62 |
| 5.2 | Additional Routines for Accessing Input Image Objects | 62 |
| 5.2.1 | HGetDRL | 62 |
| 5.2.2 | HGetFDRL | 62 |
| 5.2.3 | HGetURL | 63 |
| 5.2.4 | HGetDImage | 64 |
| 5.2.5 | HGetObjNum | 65 |
| 5.3 | Loop Macros for Accessing Single Input Objects | 65 |
| 5.3.1 | HAllObj | 66 |
| 5.3.2 | HAllComp | 66 |
| 5.4 | Creating Objects and Writing Output Object Parameters | 67 |
| 5.4.1 | HCrObj | 67 |
| 5.4.2 | HCopyObj | 68 |
| 5.4.3 | HPutDRL | 69 |
| 5.4.4 | HPutImage | 69 |
| 5.4.5 | HDefObj | 69 |
| 5.4.6 | HPutDImage | 70 |
| 5.4.7 | HCrImage | 70 |
| 5.4.8 | HCrXLD | 71 |
| 5.5 | Reading and Writing Control Parameters | 72 |

| | | |
|----------|---|------------|
| 5.5.1 | HGetPElemX | 72 |
| 5.5.2 | HGetPPar | 74 |
| 5.5.3 | HGetPElem | 74 |
| 5.5.4 | HGetCElemX | 75 |
| 5.5.5 | HGetElemX | 75 |
| 5.5.6 | HCopyElemX | 76 |
| 5.5.7 | HGetCPar | 76 |
| 5.5.8 | HGetSPar | 77 |
| 5.5.9 | HGetCParNum | 77 |
| 5.5.10 | HALlocStringMem | 78 |
| 5.5.11 | HPutPElem | 79 |
| 5.5.12 | HPutPPar | 79 |
| 5.5.13 | HPutElem | 80 |
| 5.5.14 | HPutElemH | 80 |
| 5.5.15 | HPutCPar | 80 |
| 5.6 | Auxiliary Extension Package Interface Macros and Procedures | 82 |
| 5.6.1 | HckP | 83 |
| 5.6.2 | HckNoObj | 83 |
| 5.6.3 | HRLDecomp | 83 |
| 5.6.4 | HNumOfChannels | 84 |
| 5.6.5 | HIncrRL | 84 |
| 6 | Special Routines for Typical Supply Procedures | 87 |
| 6.1 | Loop Macros | 87 |
| 6.1.1 | HAllReg | 88 |
| 6.1.2 | HAllSegm | 89 |
| 6.1.3 | HAllFilter | 90 |
| 6.1.4 | HAllFilter2 | 92 |
| 6.2 | Object Generation | 92 |
| 6.2.1 | HNewRegion | 94 |
| 6.2.2 | HPutRect | 94 |
| 6.2.3 | HDupObj | 94 |
| 7 | Creating a New HALCON Package | 97 |
| 7.1 | The HALCON Compiler 'hcomp' | 97 |
| 7.1.1 | Selection of the Host Language | 97 |
| 7.1.2 | Creating the Help Files | 98 |
| 7.1.3 | Creating HTML Reference Files | 98 |
| 7.1.4 | Creating the PDF Reference Manuals | 99 |
| 7.1.5 | Miscellaneous | 100 |
| 7.2 | Generating HALCON Packages | 100 |
| 7.2.1 | Creating the Operator Libraries | 100 |
| 7.2.2 | Creating the C Interface | 100 |
| 7.2.3 | Creating the C++ Interface | 101 |
| 7.2.4 | Creating the .NET Interface | 101 |
| 7.2.5 | Creating New Applications | 101 |
| 7.2.6 | Additional Information for Specific Platforms | 101 |
| 7.3 | HALCON Directories | 104 |
| A | HALCON Error Codes | 105 |
| B | HALCON Semantic Types | 141 |
| | Index | 143 |

Chapter 1

Introduction

HALCON can be extended by up to 99 additional operator packages. During the initialization of the system, all packages indicated by the environment variable `HALCONEXTENSIONS` are automatically loaded. A package typically contains libraries with the new operators, their prototypes, the operator information needed by `HDevelop`, and the HTML online documentation. For the programming of such a package, the HALCON Extension Package Interface is used, e.g., to manipulate parameters of HALCON operators and to read or write iconic data (images, regions, XLDs¹) from the HALCON database of iconic objects.

Furthermore, the operators provided by HALCON itself are also based on the functionality of the Extension Package Interface. Thus, the Extension Package Interface is both the interface between application programs and the operator layer of the HALCON system and the interface between the operator layer and the *iconic object database*.

A reason why to extend the capabilities of HALCON by using the Extension Package Interface might be one of the following:

- Extension of the pool of image processing operators,
- Integration of special image processing hardware,
- Integration of a special graphics software package.

The new extension package example program is an Easy Extension Interface example for .NET, and shows how to easily integrate a .NET function, based on the HALCON/.NET interface, to HALCON's operator set. It can be used within `HDevEngine` and `HDevelop`. For more information, see the `README.md` in the Easy Extension Interface for .NET example under `%HALCONEXAMPLES%\extension_package\easy_extensions\dotnet`. Once the users have extended HALCON by a package containing their own operators, these can be used within all supported host languages and the interactive tool `HDevelop`.

This chapter gives a short introduction to HALCON packages and operators, including an example describing the integration of a simple operator. The following chapters present detailed information that will allow you to write your own packages. As a common example, a package called `halconuser` will be used (see `%HALCONEXAMPLES%\extension_package\halconuser`).

Except for Linux-specific sections, file paths and environment variables are printed in the Windows convention in this manual, e.g.,

```
%HALCONEXAMPLES%\extension_package\halconuser
```

to denote the subdirectory `halconuser` containing an example package within the HALCON base directory referenced by the environment variable `HALCONEXAMPLES`. The same expression in Linux convention would look like

```
$HALCONEXAMPLES/extension_package/halconuser
```

1.1 HALCON Operators

This section describes the external interface of HALCON operators, i.e., how to use them in a programming language, and their internal structure.

¹eXtended LIne Description; i.e., subpixel contours and polygons.

1.1.1 Using HALCON Operators in C, C++, and .NET Languages

There are two different modes of calling operators from HALCON/C: One way is to call operators for simple applications with only one value per control parameter (*simple mode*). This is the easiest way and sufficient for many applications. When using complex procedures that need more than one value per parameter, data is transferred within *tuples* (`Htuple`). Iconic objects are represented with the type `Hobject`, so that one object can contain several images, regions, or XLDs.

In contrast, the HALCON/C++ and the HALCON/.NET interface support a flexible management of several types.

However, the defined class hierarchy has a fixed mapping between the HALCON operators and the provided classes. This mapping follows predefined rules and is therefore partly generic. A user-defined HALCON operator cannot be linked to an arbitrary position inside the class hierarchy. Thus, these operators are integrated using the generic data type `Hobject` in order to pass arguments to and from the operator. This kind of integration is also used, e.g., if you export your HDevelop program as C++ or C# code.

For further information on using HALCON in programming languages please refer to the [Programmer's Guide](#).

1.1.2 Internal Structure of HALCON Operators

HALCON operators (like the new operators in `halconuser`) typically consist of two procedures: One procedure – the *supply procedure* – receives the input data, tests its consistency, passes it to the processing *action procedure* and returns the output data after the processing. If the input data contains any composed iconic objects, e.g., image tuples, the supply procedure has to extract the single parts. An *iconic object key* can represent an unlimited number of iconic objects and every image object may consist of several components (one region and an unlimited number of gray value channels; see also [figure 5.2](#) on page 58). Generally, a user may assume that a HALCON operator is able to handle single iconic objects as well as composed objects (i.e., `multivalued` is set to `optional`; see [page 30](#)) and that it can work on multi-channel images (i.e., `multichannel` is set to `optional`; see [page 34](#)). So, the author of a new HALCON operator should implement appropriate mechanisms for extracting the needed data from composed iconic objects (or multi-channel images) within the supply procedure. The name of this procedure designates the internal C-procedure name specified in the DEF file (cf. [section 2.1](#) on page 19 and [section 2.2](#) on page 20).

After preprocessing the input data, the action procedure is called within the supply procedure. This procedure performs the specific image processing. In most cases the action procedure receives only the already extracted single components (e.g., regions of type `Hregion`, channels of type `Himage`, or pointers to the raw image data) and parameter values. The results are returned to the supply procedure where they are passed to the generated interface that returns them to the calling system. Every supply procedure returns an error code of type `Herror`. Thus, it is necessary to return an error code, which is `H_MSG_TRUE` if no error occurred.

Only one parameter (a so called procedure handle) is passed to a supply procedure. All other input data (iconic objects and control values) is read and written with the help of this identifier. Moreover, it allows the unique identification of a HALCON operator call while running HALCON on parallel hardware. Instead of further parameters, all in- and output to and from the supply procedure is done with the help of several (internal) buffers, as illustrated in [figure 1.1](#).

The buffer contains input data as well as output data. Control parameters (containing all kind of control values like integers, floating-point values, strings or handles) are stored directly in the buffers, whereas all iconic data (including images, regions and XLDs) are stored in the database and represented by an iconic object key. Iconic data can be accessed with the help of database procedures by using these keys. The Extension Package Interface provides special procedures and macros for reading and writing elements of the parameter buffer within the supply procedure. Every parameter belongs to one of the four classes

- input iconic object
- output iconic object
- input control parameter
- output control parameter

that determines the name of the suitable procedures/macros (e.g.: `HGetCPar` is used to *get* an input control value). To identify a specific parameter within a class, its number is passed to the procedure/macro. This is the number of




Figure 1.1: Data flow within HALCON.

the parameter within the parameter-list of a HALCON operator counted for every parameter class (e.g.: to get the value of the *second* input control parameter, the number 2 must be passed to HGetCPar).

The read-/write access on the buffer is done automatically by the generated interface. The code of this interface is generated by the HALCON compiler `hcomp` (see [page 16](#) and [section 7.1](#) on [page 97](#)) from a so-called *definition file* (DEF file). Any programmer of a new HALCON operator must provide such a definition file, which contains all relevant information, e.g., concerning in- and output parameters: information about the parameter class (input-/output, iconic object/control), about the parameter type, etc. The syntax and semantics of the definition file is explained in [chapter 2](#) on [page 19](#).

1.2 HALCON Packages

Similar to the standard HALCON system a programmer has to provide (at least) two libraries (DLLs in Windows, shared libraries in Linux environments) in order to extend HALCON by a new operator package (see [chapter 7](#) on [page 97](#)).

- A library containing the new operators (written in C). Most of this manual is about how to write such operators based on internal data structures / procedures of the HALCON system. This library has the same name as the package itself, in our example `halconuser`.
- Libraries encapsulating the generated interface code (for C, C++, .NET). These libraries (i.e., the operator library and one of the interface libraries) have to be used in new applications in order to provide the interface of the new operators to the host language of your choice. Most of the work concerning these libraries is done by the HALCON compiler `hcomp`, see [section 7.1](#) on [page 97](#) for details. In the example package these libraries are called `halconuserc`, `halconusercpp`, and `halconuserdotnet`.

The names of all these libraries are derived from the name of the package itself: A package `package` contains the libraries² `package`, `packagec`, `packagecpp`, and `packagedotnet`.

²This is true for the Windows version. For Linux, the prefix `lib` is added to the libraries, resulting in `libpackage`, `libpackagec`, and `libpackagecpp`.

1.2.1 Packages and HALCON XL

Extension packages can also be used in HALCON XL. Similar to the HALCON libraries, which exist in two versions (e.g., `halcon.dll` and `halconxl.dll`), you must provide separate versions of your package libraries to be used together with HALCON XL. The names of these libraries must have the suffix `xl`; e.g., the HALCON XL version of the example package `halconuser` consists of the libraries `halconuserxl.dll`, `halconusercxl.dll`, `halconusercppxl.dll`, and `halconuserxxl.dll` (Windows), `libhalconuserxl.so`, `libhalconusercxl.so`, and `libhalconusercppxl.so` (Linux), and `halconuserdotnetxl.dll` (.NET).

The HALCON XL version of the libraries is created analogously to the standard HALCON version with only small differences. See [section 7.2](#) on page 100 for details.

1.2.2 Directory Structure of a HALCON Package

A HALCON package resides in a directory with the same name as the package itself. In our example this is the directory `halconuser` in `%HALCONEXAMPLES%\extension_package`. This directory must at least contain the following subdirectories

- `bin\%HALCONARCH%`: For Windows, this subdirectory has to contain the DLLs `package.dll`, `packagec.dll`, and `packagecpp.dll`, corresponding to the above libraries (and their HALCON XL versions). We also recommend to place compiled example programs or additional utilities of a package in this subdirectory.
- `lib\%HALCONARCH%`: In this subdirectory the libraries encapsulating the new operators (`package`) and the corresponding C and C++ language interfaces (`packagec`, `packagecpp`) reside³, together with their HALCON XL versions. **Note that neither the name of these libraries nor their position within the package should be changed.** Otherwise, the HALCON system cannot load the package. The environment variable `HALCONARCH` is set during the installation of HALCON; it describes the platform HALCON is running on. See the Installation Guide, [section 1.4](#) on page 8, for details.
- `bin\dotnet`: This subdirectory has to contain the extension package's .NET assembly `packagedotnet.dll` (and its HALCON XL version, `packagedotnetxl.dll`).
- `help`: This subdirectory contains files with data for the online access to the knowledge base. They *must* be generated and placed in this directory in order to use a package inside of HDevelop. Without these files HDevelop cannot retrieve the information needed to access the operators of a package.

We also recommend providing additional subdirectories:

- `def`: In this directory the DEF file(s) with the description of the operators of a package should be placed.
- `include`: In this directory the generated include files containing the prototypes for the operators of a package should be placed.
- `doc`: In this directory the documentation of the package should be placed (see also `%HALCONROOT%\doc` for comparison). Especially, it is necessary to put the generated HTML files in `doc\html\reference` in order to enjoy the online help from the operator window of HDevelop.
- `examples`: This directory might contain some typical example programs (e.g., HDevelop dev-files) demonstrating the use of the new operators.
- `images`: If the provided examples need specific images, they should be placed in this directory. In that case we recommend including the path to this subdirectory in the environment variable `HALCONIMAGES` to allow access to these images without using an absolute file path in the programs.

³For Linux systems the prefix `lib` has to be added to the libraries resulting in `libpackage`, `libpackagec`, and `libpackagecpp`

1.2.3 How to Create and Use a HALCON Package

In summary, the following steps are necessary to create a HALCON package with the name `package` integrating new operators into the HALCON system. As noted in [section 1.2.1](#), to create a HALCON XL package, you must create a second version of the libraries. A detailed description of the steps can be found in the referenced sections of this manual:

1. Description of the new operator(s) in one or more DEF files (cf. [chapter 2](#) on page 19). We recommend placing these files in the package subdirectory `def`.
2. Creation of a library (called `package`) containing the supply procedures in C and the corresponding action procedures (cf. [chapters 3](#) to [6](#)). This library has to be placed in the package subdirectory `lib/$HALCONARCH` (Linux) or `bin\%HALCONARCH%` (Windows).
3. Creation of a library containing the language-dependent operator interfaces (`packagec`, `packagecpp`, `packageex`, and `packagedotnet`) based on the DEF files with the help of `hcomp` (cf. [section 7.1](#) on page 97). These libraries have to be placed in the subdirectory `lib/$HALCONARCH` (C, C++ under Linux) or `bin\%HALCONARCH%` (C, C++ under Windows) or `bin\dotnet` of the package.
4. Generation of files for online access to the knowledge base with the help of `hcomp`. These files are used, e.g., by `HDevelop`. They have to be placed in the subdirectory `help` of the package.
5. Generating the HTML reference files with the help of `hcomp` (optional). The generated files have to be placed in the subdirectory `doc\html\reference` of the package.
6. Generating PDF manuals with the help of `hcomp` (optional).
7. Extension of the package list in the environment variable `HALCONEXTENSIONS` by the *complete* file path of the new package, e.g.,

```
%HALCONEXAMPLES%\extension_package\halconuser
```

For some platforms, additional environment variables have to be modified; see [section 1.3](#) and [section 7.2.6](#) on page 101.

8. Linking of the generated libraries together with the HALCON library to the image analysis application (cf. [chapter 7](#) on page 97). For this, you have to modify additional environment variables, depending on the operating system (see below). Please note that `HDevelop` is able to access the new operators dynamically without linkage.

1.3 Installing a HALCON Package

To install a HALCON package you have to copy the package to your hard disk and add the *complete* path of the package to the environment variable `HALCONEXTENSIONS`, e.g.,

```
%HALCONEXAMPLES%\extension_package\halconuser
```

Note that the delimiter between paths in an environment variable is a semicolon on Windows systems and a colon on Linux systems. **Never change the name of a package or the corresponding names of the libraries or DLLs contained in a package.** These names are encoded *within* the libraries/DLLs. If you change the names this information will not match any longer. Thus, the loader of the operating system will fail to open the dynamic libraries. To use the new package within `HDevelop`, you have to **restart** the program. For generating a stand-alone application using the package you have to link the C or C++ interface library, or reference the .NET assembly of the package in the application code, see [section 7.2](#) on page 100.

If the package contains images used, e.g., within example programs you might want to include the corresponding directory (e.g., `images` within the package) in the environment variable `HALCONIMAGES` to access those images without specifying a complete path.

Furthermore, you must modify additional environment variables in order to use your new package (see below).

1.3.1 Additional Information for Windows

To be able to link the package DLL to your application program, the *complete* DLL file path of the new package, e.g.,

```
%HALCONEXAMPLES%\extension_package\halconuser\bin\%HALCONARCH
```

has to be added to the environment variable PATH, see [section 7.2.6.1](#) on page 101.



Do not copy a package DLL into the Windows system directories, as it would be loaded twice in this case!

Note that you must extend the variable PATH also for .NET applications, even if you do not explicitly link the main package library (package.dll): The referenced .NET assembly automatically loads this library.

1.3.2 Additional Information for Linux

On Linux systems you have to include the package library subdirectory lib/\$HALCONARCH in the environment variable LD_LIBRARY_PATH in order to use a package.

This has to be done in *any* case – regardless whether you plan to use a package within HDevelop only or you want to create stand-alone applications.

For .NET applications, an alternative to setting LD_LIBRARY_PATH is described in the Programmer's Guide in [section 12.2.3](#) on page 87.

1.4 An Example

The following example illustrates the steps described in [section 1.2](#) on page 11. Assume, one wants to implement a new operator named `user_thresh` to extract all pixels with a gray value larger than a threshold value specified in an input parameter. The use of `user_thresh` within a C program is illustrated in [figure 1.2](#); a more detailed example is provided in `%HALCONEXAMPLES%\extension_package\halconuser\source\testthreshold.c`.

```
main()
{
    Hobject    Image,Region;
    int        Thresh;

    read_image(&Image,"monkey");
    Thresh = 100;
    user_thresh(Image,&Region,Thresh);
}
```

Figure 1.2: Calling the operator `user_thresh` in C.

To use `user_thresh` in this way within C programs⁴,

- The new operator must be implemented.
- The corresponding HALCON interface code must be generated.
- The corresponding package must be created especially containing the operator and interface libraries.
- The application must be linked.

First of all one has to create a *definition file* (file extension `.def`), as illustrated in [figures 1.3](#) and [1.4](#). [Figure 1.3](#) shows only the absolute minimum of information that a definition file must contain in order to call a new operator within C programs. When using HDevelop, C++, or C#, an extended version is necessary as described in [section 2.2](#) on page 20. The minimal form of such an extended definition is illustrated in [figure 1.4](#). The definition file specifies:

⁴To use it within C++, C#, or Visual Basic basically the same steps are necessary, see [chapter 7](#) on page 97.

```
user_thresh <- CIPUserThreshold[Image:Region:Threshold$i:];
```

Figure 1.3: Defining a new operator `user_thresh`.

```
user_thresh <- CIPUserThreshold[Image:Region:Threshold:]

short.german
  Schwellenwert-Operator.;

short.english
  Selection of gray values by thresholding.;

module
  foundation;

chapter.german
  BenutzerErweiterungen;

chapter.english
  UserExtensions;

functionality
  image;

parameter
  Image:          input_object;
  sem_type:      image;

parameter
  Region:         output_object;
  sem_type:      region;

parameter
  Threshold:      input_control;
  default_type:  integer;
  multivalued:   false;
  sem_type:      number;
```

Figure 1.4: An example for an extended DEF file of the operator `user_thresh` (minimal form), cf. `%HALCONEXAMPLES%\extension_package\halconuser\def\threshold.def`.

- the name of the operator (`user_thresh`),
- the name of the supply procedure that has to be implemented in C (`CIPUserThreshold`),
- names and types of the operator's parameter(s). The names of the parameters are only important for the manuals and within HDevelop.

The minimal form of the extended operator DEF file includes: A short description (`short`), the HALCON module (`module`) the operator belongs to, the mapping to a chapter (`chapter`) of the manual, the mapping to an iconic object (`functionality`), and for every parameter its semantic type (`sem_type`). In addition, the type (`default_type`) and number (`multivalued`) must be specified for control parameters.

Our operator `user_thresh` has got the following parameters:

- one input iconic object parameter (`Image`),
- one output iconic object parameter (`Region`),
- one input control parameter (`Threshold`) of type `int` with exactly one value and
- no output control parameter.

The operator definition within the DEF file now is used by `hcomp` to generate the appropriate interface code. [figure 1.5](#) shows the calls of `hcomp`. Note, that within this manual `halconuser` is used as name of the HALCON

```
hcomp -u -H -phalconuser threshold.def
hcomp -u -C -phalconuser threshold.def
```

Figure 1.5: Calls of `hcomp` for HALCON/C.

package to be created. By calling `hcomp` with these options⁵ the files `Hhalconuser.c` (HALCON interface code), `HChalconuser.c` (C-specific interface code) and `HChalconuser.h` (prototype of the new HALCON operator) are created.

In the next step one has to program the new HALCON operator. This is done by implementing the supply and action procedure. This results in the typical structure of HALCON operators as illustrated in [figure 1.6](#).

```
/* action procedure */
Error IPBThreshold(proc_handle,region,image,
                  width,threshold,region_out)
{
    ...
}

/* supply procedure - always with this parameter! */
Error CIPUserThreshold(Hproc_handle proc_handle)
{
    HGetCPar(...,&Threshold,...);          /* get control */
                                          /* parameter */
    HAllSegm(proc_handle,&region,&image,1,i) /* work on all */
                                          /* input images */
    {
        HChkP(proc_handle,IPBThreshold(...)); /* call action */
                                          /* procedure */
        HNewRegion(proc_handle,region_out); /* store (result) */
                                          /* region */
    }
    return(H_MSG_TRUE);
}
```

Figure 1.6: Sample source code of supply `CIPUserThreshold()` and action `IPBThreshold()` procedure.

Compiling the source code generates an object file (in the example `cipuserthreshold.o`) that should be integrated into the user extension library (`halconuser`). Moreover, the generated interface code must be converted to the corresponding language dependent interface library: In case of a C application, this is `halconuserc` containing `HChalconuser.o`. The example CMake file `CMakeLists.txt` in the directory `%HALCONEXAMPLES%\extension_package\halconuser` can be used for generating the example package under Linux or Windows and test programs as well.

Now we can use our new operators within C programs. But they are not yet available within `HDevelop`, because the online help files have not been generated so far. There is also still missing any kind of documentation, such as the HTML manual pages.

```
hcomp -u -M threshold.def
```

Figure 1.7: Calling the HALCON compiler `hcomp` to create the help files.

The online help files (as they are used e.g., by `HDevelop`) can also be generated with the help of the HALCON compiler `hcomp`, see [figure 1.7](#). However, to do so an extended version of the DEF file must be available. The generated help files must be placed in the subdirectory `help` of the package.

The help files generated by now are used to access information about the new operators by calling specific HALCON operators like `get_operator_info`. This is important especially for constructing graphical user interfaces

⁵see [section 7.1](#) on page 97 for a complete description.

like HDevelop. For the user a more convenient way to access information online is to browse through HTML documents. The HTML documentation of HALCON operators can be generated by `hcomp` as well. The HTML files have to be placed in the corresponding subdirectory `doc\html\reference` of the package.

If you now add the package path to `HALCONEXTENSIONS` and start HDevelop the user extensions, e.g. `user_thresh`, are automatically available in the specified menu (i.e., chapter). In our example this menu is called `UserExtensions` as specified in `%HALCONEXAMPLES%\extension_package\halconuser\def\threshold.def`.⁶ You can select and execute the user-defined operators like all the built-in operators of the HALCON system. The HTML documentation is available via the `Help` button within the operator window.

Examples of how to use the user defined extensions in HDevelop can be found in the subdirectory `examples` of `%HALCONEXAMPLES%\extension_package\halconuser (*.dev)`. Furthermore, the `*.dev` programs have been exported as C++ and C programs. The `*.cpp` and `*.c` files can be found in the subdirectory `source`. You can compile them using the already mentioned `CMake` file. These `*.cpp` and `*.c` files also serve as an example for the integration of user defined operators into the host languages C++ and C. Note that before compiling the *exported* C++ and C code containing operators from the package `halconuser`, the corresponding user extension libraries have been created. This can be done via the `CMakeLists.txt` in `%HALCONEXAMPLES%\extension_package\halconuser` which will also generate the needed user extension C++ library `halconusercpp` and C library `halconuserc`.

Please note that on some systems not all users have write permissions in the directories mentioned above. To experiment with the example package we recommend to create a private copy in your working directory. In such a case you must of course use the actual path to your copy when modifying environment variables.

⁶`UserExtensions` is integrated into the menu `Operator` of HDevelop.

Chapter 2

Operator Description (DEF File)

Note that DEF files with non-ASCII characters should be UTF-8 encoded.

The following chapters give a detailed description of the steps mentioned in [chapter 1](#) on page 9. This is done with respect to system-defined HALCON operators as well as to the examples within the directory %HALCONEX-AMPLES%\extension_package\halconuser. We start with the generation of an operator description.

2.1 Short Operator Description

Before implementing an operator the author should think about the task of the operator and what kind of user interface is best for calling the operator. This specification is used to automatically generate the interface code for the desired host language with the HALCON compiler `hcomp`.

To do this, it is necessary to describe at least the following features beside the operator name in a DEF file:

- the name of the operator as used within the application programming language,
- the name of the C-procedure (supply procedure) called by HALCON in order to start the processing (this procedure must be implemented later on),
- all iconic objects and control parameters that are needed by the operator as input (input parameters),
- all iconic objects and control parameters that are returned by the operator as result (output parameters),
- the types of these parameters,
- the number of values per parameter (there is only a distinction between parameters that need or can process *exactly one value* and those expecting *more than one value*).

There exist two kinds of parameters within HALCON: Iconic object parameters and parameters containing *any other data* – so called *control parameters*. By distinguishing input and output parameters we get four parameter classes: *Input iconic object parameters*, *output iconic object parameters*, *input control parameters*, and *output control parameters*. Basically, specifying the number of parameters per class would suffice to describe the operator. The internal access (in particular within the supply procedure) on individual parameters works this way by using the parameter's position within its class. But to refer to single parameters and add further information regarding a parameter, it is useful to give it a name.

The information specified up to now is already sufficient to integrate an operator within the HALCON/Extension Package Interface by using `hcomp`. It describes the operator properly and may be specified as a “one line short version” of the DEF file according to the following syntax:

```
extern_operator_name <- InternCProcedure  
  [InputObjects:OutputObjects:InputCtrlParams:OutputCtrlParams];
```

[Section 2.2](#) explains the meaning of the single identifiers and the name convention. Please note that in contrast to the header mentioned there, the short version header must be finished by a semicolon (;) and that the default type and the number of values is specified together with the name of a control parameter (InputCtrlParams and

```
user_inside <- CIPUserSelect [Regions:RegionSelected:Row$i,Column$i:];
```

Figure 2.1: Short version of the definition of the operator `user_inside` (cf. `%HALCONEXAMPLES%\extension_package\halconuser\def\regionfeatures.def`).

`OuputCtrlParams`). This is done by concatenating a dollar sign and an additional character to the name encoding the type and number of values (cf. the example in [figure 2.1](#)).

The following table shows how to code types and number of values into a character. Lower-case characters stand for *exactly one value* in the specified parameter. This corresponds to assigning `multivalue: false` in the extended version. Capital letters specify parameters that contain *one or more than one value* (`multivalue: optional`).

| Type | C-type | Code | |
|----------------------|--------|-----------|------------------|
| | | One Value | Unlimited Number |
| Integer | long | i | I |
| Floating-point Value | double | f | F |
| String | char * | s | S |

The specification described so far is sufficient to integrate the operator into C applications. However, in general the new operators should also be usable by HDevelop or within C++ or .NET applications. To achieve this, an extended version of the operator description must be generated. This is described in the following section.

2.2 Extended Operator Description

An operator description within a DEF file must start with a header. The following entries are variable in their order. All of these slots begin with a determined keyword and are finished by a semicolon (;). Semicolons within the text not defining the end of a slot must be quoted with a backslash (\;).

Some slots are language dependent: For example `short.english` contains a short description of the operator in *English*, `short.german` the same description in *German*. The currently supported languages are English and German. In order to allow an international usage of operators we strongly recommend always to provide all `.english` slots.

Note that all slots specified within the operator description are accessible online within the HALCON system using the operator `get_operator_info`, see the Reference Manuals for details. Describing the single parameters completes the operator description. [Section 2.3](#) on page 28 explains how to do this.

2.2.1 Header

The operator description starts with the header

```
extern_operator_name <- InternCProcedure
    [InputObjects:OutputObjects:InputCtrlParams:OuputCtrlParams]
```

Note that in contrast to the short version described in [section 2.1](#), the header doesn't contain any information about the types of the control parameters (e.g. `$f`) and does not end with a semicolon (;).

The following example is a short version of the operator description for the dynamic threshold operator `dyn_threshold`. For better legibility there should be a comment at the beginning of every operator description, like

```
/****** dyn_threshold *****/
dyn_threshold <- CIPDynThreshold
    [OrigImage,ThresholdImage:RegionDynThresh:Offset,LightDark:]
```

Comments within DEF files are indicated according to the C syntax (`/* ... */`).

There are a couple of conventions/restrictions concerning the names of parameters: All word parts should begin with a capital letter (e.g., `RegionDynThresh`). They are directly concatenated without any separating character. Especially, they must not contain any underscore ('_')! The external operator name exclusively consists of lower-case characters with word parts separated by underscores. This operator name is used within C programs, low-level calls¹ of the operator in C++, or within HDevelop.

The four parameter classes (input-/output iconic object/control) are separated by colons (:). One class is described by a list of all parameter names within the class separated by commas. If there is no member of a class for an operator, the list remains empty. The example described above defines the following mapping between parameters and parameter classes:

| parameter class | keyword (cf. page 29) | parameter in the example |
|---------------------------|--|--|
| input iconic objects | <code>input_object</code> | <code>OrigImage, ThresholdImage</code> |
| output iconic objects | <code>output_object</code> | <code>RegionDynThresh</code> |
| input control parameters | <code>input_control</code> | <code>Offset, LightDark</code> |
| output control parameters | <code>output_control</code> | <code>∅</code> |

It is helpful to follow certain conventions, when choosing names for parameters. They should be meaningful (i.e. one should avoid names like 'Aac') and consequently should be given in English. It is convention to denote parameters that specify a position within an image matrix by *Row(s)* (not *Line!*) and *Column(s)* or *Col(s)*. Parameters defining a dimension are called *Width* and *Height*.

2.2.2 short

The keyword `short` starts the short description of the operator, in our example

```
short.english
  Segment an image using a local threshold.;
```

As all slots specified by the keyword `.english`, this slot contains purely textual information. Text can be written in different languages and can contain \LaTeX -commands according to special syntactic rules that are defined in [section 2.4](#) on page 35.

2.2.3 warning

With the slot `warning`, you can show a warning text in bold at the beginning of an operator description, for example

```
warning.english
  This operator is obsolete.;
```

As all slots specified by the keyword `.english`, this slot contains purely textual information. Text can be written in different languages and can contain \LaTeX -commands according to special syntactic rules that are defined in [section 2.4](#) on page 35.

2.2.4 abstract

A more detailed description of the operator is given within the slot `abstract`. The description of the example is here shown as a shortened version:

¹Within the HALCON/C++ and HALCON/.NET class hierarchy corresponding *methods* use slightly different conventions: `extern_operator_name` is transformed into `ExternOperatorName`.

```

abstract.english
\OpRef{dyn_threshold} selects from the input image those regions in which the
pixel fulfill a threshold condition. Let  $g_{\{o\}} = g_{\{\text{\ParRef{OrigImage}\}}}$ ,
and  $g_{\{m\}} = g_{\{\text{\ParRef{ThresholdImage}\}}}$ . Then the condition for
\ParRef{LightDark} = \ValRef{'light'} is:
@a
           $g_{\{o\}} \geq g_{\{m\}} + \text{\ParRef{Offset}}$ 
@l\[
   $g_{\{o\}} \geq g_{\{m\}} + \text{\ParRef{Offset}}$ 
\]
@e
For \ParRef{LightDark} = \ValRef{'dark'} the condition is:
@a
           $g_{\{o\}} \leq g_{\{m\}} - \text{\ParRef{Offset}}$ 
@l\[
   $g_{\{o\}} \leq g_{\{m\}} - \text{\ParRef{Offset}}$ 
\]
@e
Finally, for \ParRef{LightDark} = \ValRef{'equal'} it is:
@a
           $g_{\{m\}} - \text{\ParRef{Offset}} \leq g_{\{o\}} \leq g_{\{m\}} + \text{\ParRef{Offset}}$ 
@l\[
   $g_{\{m\}} - \text{\ParRef{Offset}} \leq g_{\{o\}} \leq g_{\{m\}} + \text{\ParRef{Offset}}$ 
\]
@e
This means that all points in \ParRef{OrigImage} for which the gray value is
larger or equal to the gray value in \ParRef{ThresholdImage} plus an offset
are aggregated into the resulting region.;

```

Again, refer to [section 2.4](#) on page 35 for the special syntax of text.

2.2.5 module

```

module
  foundation;

```

This slot denotes the module inside HALCON the operator should belong to. For user extensions the module 'foundation' is recommended.

2.2.6 chapter

To achieve a useful structuring of HALCON operators, they are all arranged in a hierarchy of chapters and sections. The assignment defined in the slot chapter is reflected in the reference manuals and in the menu Operator of HDevelop.

```

chapter.english
  Segmentation;

```

The structuring can be refined by specifying a section: chapter[,section], e.g.,

```

chapter.english
  Filter,Edges;

```

Note that it is not allowed to insert operators and sections into the same chapter at the same level of hierarchy. So if you decide to use sections within a chapter, *all* operators within this chapter must be assigned to one of these sections.

The chapters and sections created using the slot chapter may be supplemented by an optional chapter description as described in [section 2.5](#) on page 38.

2.2.7 functionality

```
functionality
  image;
```

This slot denotes the class of which the operator should become a method within an object-oriented programming language like C++ or C#². Generally this corresponds to the semantic type of the first parameter, e.g., an image object (`image`). The specified name is only a symbolic one. The actual class name depends on the programming language and is provided by the HALCON compiler `hcomp`. Possible values for `functionality` in the current version are

```
any, window, image, region, object, xld_cont, xld_poly, xld_para, xld_mod_para, xld_ext_para
```

2.2.8 keywords

Furthermore, one can assign a list of keywords to an operator. They are used e.g., by `HDevelop` to support the search for the proper operators for a given problem.

```
keywords.english
  threshold, gray-value threshold, dynamic threshold, local threshold;
```

2.2.9 predecessor, successor, alternatives

The following slots also support interactive development of image processing application with HALCON. They are used to define potential, convenient or necessary predecessor (`predecessor`) and successor operators (`successor`) or to define alternatives (`alternatives`). All operators within these lists are referenced by their name.

```
predecessor
  mean_image, smooth_image, gauss_image;

successor
  connection, select_shape, reduce_domain, select_gray, rank_region,
  dilation1, opening;

alternatives
  highpass, threshold, background_seg;
```

2.2.10 see_also

The slot `see_also` contains a list of operators that are used for similar tasks or help to understand how an operator works.

```
see_also
  mean_image, smooth_image, gauss_image, connection, rank_region, dilation1;
```

2.2.11 attention

The slot `attention` contains hints for using the operator or specific limitations.

²User-defined extensions are not inserted in the class hierarchy but considered as global methods.

```
attention.english
  If \ParRef{Offset} is chosen from @a -1 .. 1 @l$-1\dots1$@e
  usually a very noisy region is generated, requiring large storage.
  If \ParRef{Offset} is chosen too large ($>$ 60, say) it may happen
  that no points fulfill the threshold condition (i.e.\ an empty
  region is returned). If \ParRef{Offset} is chosen too small ($<$
  -60, say) it may happen that all points fulfill the threshold
  condition (i.e.\ a full region is returned).;
```

2.2.12 result_state

The slot `result_state` defines the result value of an operator and the corresponding exception handling. The syntactical rules for the text are again the same as described in [section 2.4](#) on page 35.

```
result_state.english
  \OpRef{dyn_threshold} returns 2 (H\MSG\TRUE) if all parameters are
  correct. The behavior with respect to the input images and output
  regions can be determined by setting the values of the flags
  \ValRef{'no_object_result'}, \ValRef{'empty_region_result'}, and
  \ValRef{'store_empty_region'} with \OpRef{set_system}.
  If necessary, an exception is raised.;
```

2.2.13 parallelization

The slot `parallelization` results in the manual entry `Execution Information`. It contains information about the timeout and parallelization characteristics of the operator. On the one hand, this regards the possibility of using the operator in a parallel, for example, multithreaded application and on the other hand this regards the automatic parallelization which HALCON uses to speed up the operator's processing when working with multi-processor or multi-core hardware.

The slot `parallelization` consists of several sub-slots, each starting with a characteristic keyword followed by a colon and finishing with a semicolon. The example below shows the slot for the operator `dyn_threshold`, which is not "local", needs neither complete nor mutual exclusion, and is parallelized on tuple and domain level. The single subslots and their meaning will be described in the following sections.

```
parallelization
  process_exclusively:  false;
  process_locally:     false;
  process_mutual:      false;
  method:              split_tuple, split_domain;
  region_postprocessing: domain_concat_si_inp;
```

- `process_exclusively: true, false, none;`
This subplot of `parallelization` assigns whether an operator is processed *completely exclusively* ('true') by the main HALCON process/thread or not. An exclusive processing means that no other operator will be processed by HALCON while the exclusive operator is running. If an exclusive operator is started and other operators are still running, the processing of the exclusive operator is delayed until all other (currently running) operators have completed.

An exclusively processed operator is always processed *without* any parallelization by the main HALCON thread/process. Note that even if HALCON is reentrant for most of the operators, there are still some operators that have to be processed exclusively due to reasons of their implementation.

If no subplot `process_exclusively` is filled in with an operator, it is assumed that the operator needs no completely exclusive processing ("optimistic" assumption).

If the subplot contains `none`, the operator is processed by HALCON independently of other operators (even exclusive ones). This value is only used internally by MVTec.

- `process_mutual: true, false;`
This subplot of `parallelization` assigns whether HALCON processes an operator under *mutual exclusion* ('true') against itself or not. Here, a mutual exclusion means that the same operator may not run twice or more at the same time (but other HALCON operators can).

An mutually processed operator is always processed *without* any parallelization by the main HALCON thread/process.

If no subplot `process_mutual` is filled in with an operator, it is assumed that the operator needs no mutual exclusion ("optimistic" assumption).

- `process_locally: true, false;`
This subplot of `parallelization` assigns, whether an operator must be processed locally ('true') by a program thread, or whether it may called by any ("external") thread without problems.

If `process_locally` is set to 'true', this signals the programmer that the corresponding operator must be used carefully within multithreaded applications. The simplest way to avoid any problems with such operators is to process them all under mutual exclusion within the main thread of the program.

As a side effect, HALCON processes an operator *without* parallelization regardless the settings of the subplots `method` and `domain_split`, if `process_locally` is set to 'true'. This avoids problems with 'local' operators and multithreading and makes sense because 'local' operators normally are responsible for graphical interaction and thus are not suitable for parallelization.

If no subplot `process_locally` is filled in with an operator, it is assumed that the operator must be processed "locally" ("pessimistic" assumption). However, this subplot should be filled in in any case, because it contains a very useful information for programmers of multithreaded applications.

- `method: none, split_tuple, split_channel, split_domain, split_partial, split_partial_domain;`
This subplot of `parallelization` can contain one or more of the strings above and specifies, which type of (automatic) parallelization the operator is suitable for:
 - `none`: HALCON does not automatically parallelize the operator.
 - `split_tuple`: HALCON parallelizes the operator by splitting every input image tuple into several subsets of the tuple; the tuple subsets are then processed in parallel.
 - `split_channel`: HALCON parallelizes by splitting every multichannel (input) image into several subsets of the channels; the subsets are then processed in parallel.
 - `split_domain`: HALCON parallelizes by splitting the domain of every input image into several parts; the parts are then processed in parallel.
 - `split_partial, split_partial_domain`: These methods are only used by MVTec to indicate the internal parallelization of HALCON operators.

If `method` is set to anything other but 'none', the *parameter* slot `costs_weight` *must* be filled in for every input control parameter and the *parameter* slot `postprocessing` *must* be filled in for every output control parameter of the operator (see [page 31](#))!

If `method` is set to 'split_domain', the slot `region_postprocessing` (see below) must also be set correctly and may not be omitted!

If the slot `process_locally` is set to 'true', `method` should be set to 'none', because the operator won't be parallelized then (see description of `process_locally` above).

Note that the slot `method` may contain any combination of the strings 'split_tuple', 'split_channel', and 'split_domain', because an operator may be parallelized by using any combination of those three methods. However, if 'none' is specified with the slot `method`, no other string should be specified with it in order to keep the description consistent.

If no slot `method` is filled in with an operator, it is assumed that the operator is *not* suitable for being automatically parallelized ("pessimistic" assumption).

- `region_postprocessing: none, domain_concat_si_inp, domain_concat_mult_inp;`
This subplot of `parallelization` must (only) be set for operators that are suitable for being parallelized by splitting the domain of input objects (i.e. slot `method` contains 'split_domain'). For such operators HALCON supports a simple postprocessing of output region components: After splitting the domain of input objects and processing the operator in parallel (within the subparts of the original domain), HALCON

creates the overall output iconic objects based on the output objects of the parallel processing. At this, it supports three methods for determining the domain/region components of overall output objects. Those three methods correspond to the three possible values of `region_postprocessing`:

- `none`: no postprocessing of region/domain components. Here, HALCON directly adopts the region components of input objects and re-uses them unchanged as the region components of the corresponding overall output objects. This method is especially suitable for operators which output solely *image* objects and where the domain is left unchanged, such as filter operators (e.g. `mean_image`).
- `domain_concat_si_inp`: postprocess region components by **concatenation** for operators which have only a **single input** iconic parameter. Here, HALCON creates the region components of *overall* output objects by concatenating the region components of the corresponding output objects of the parallel processing. At this, the latter regions must not overlap! Therefore, `domain_concat_si_inp` can only be used for operators, for which the subplot `domain_split` (see below) is set to '0'. This method is suitable, for example, for the operator `threshold` which outputs a region containing all pixels of a certain gray value range. Here, HALCON splits the input domain into disjunctive parts, processes the threshold operator in parallel, and finally concatenates the single result regions to one overall result region.
- `domain_concat_mult_inp`: postprocess region components by **concatenation** for operators which have **multiple input** iconic parameter and which need a specific handling of the input objects. This method is quite similar to that above, i.e., HALCON also creates the region components of *overall* output objects by concatenating the region components of the corresponding output objects of the parallel processing. Again, the latter regions must not overlap! Therefore, `domain_concat_mult_inp` can only be used for operators, for which the subplot `domain_split` (see below) is set to '0'. For `domain_concat_mult_inp` HALCON uses a specific handling of input objects. Normally, HALCON splits the domains of *all* objects of all input iconic parameters in the same manner (e.g. by splitting into the first and the second half of the chords, independent from the row index of the chords). This does not mean any problem as long as all input image domains are the same — especially, if domains of corresponding objects of *different* input parameters are the same. Because then also the *split* domains will match each other. This is not the case, if we have to expect that domains of objects of different input iconic parameters may differ. Here, it may happen that split domain parts of the first parameter and that of the second parameter do not overlap because of the simple splitting mechanism which does not take into account the row index of chords. If so, and if an operator uses, for example, an intersection of the input domains of different input parameters for defining the valid domain of the processed operation, it would get an empty region — in contrast to the sequential processing of the same operator. Therefore, we must assign `domain_concat_mult_inp` for such operators. This will force HALCON to only split the domains of the objects of the *first* input iconic parameter. The domains of input objects of all other input iconic parameters are left unchanged so that they fit to the domains of the first input iconic parameter regardless of their position in the image. This method is suitable, for example, for the operator `add_image` which adds two images and sets the domain of the result image to the intersection of the domains of the two input images. By defining `domain_concat_mult_inp` for `add_image`, HALCON only splits the domain of the first image to add, then calculates the intersection of the split domain parts with the unchanged domain of the second image in parallel, performs the addition of gray values in parallel, and finally merges the resulting region components (domains) by concatenation into the region component of the overall output image which also contains the added gray values.
- `abort_mode`: `break`, `cancel`, `both`;
This subplot of parallelization must only be used to determine the supported timeout mode. In case no timeout is supported, this slot must be omitted. For an explanation of the different modes, see the reference manual entry for `set_operator_timeout`.

Though, we recommend to specify the whole slot `parallelization`, it is also possible to completely leave it out in an operator's description. In this case, it is assumed that the operator is *reentrant*, i.e. it is *not* processed under (complete or mutual) exclusion, and that it must be processed "locally". The latter also means that *no* parallelization is used when processing the operator. This assumption corresponds exactly to those which are used in the case of missing single subslots (see descriptions above).

2.2.14 complexity

The slot `complexity` describes the complexity of the operation in terms of number of points along a contour, the area of an image region etc.

```
complexity.english
  Let  $F$  be the area of the input region. Then the runtime
  complexity is  $O(F)$ .
```

2.2.15 example

It is possible to describe an example under the keyword `example` in order to illustrate the usage of an operator. An extension of the keyword specifies the programming language of the example.

```
example.trias
  /* Looking for regions with the diameter D: */

  mean_image(Imaged,Mean,D*2,D*2)
  dyn_threshold(Image,Mean,Seg,5,'light')
  connection(Seg,Objects);
```

The extension `.trias` indicates a HDevelop example. Moreover, the extensions `.c`, `.cpp`, and `.c#` can be used. The text of the example is processed unmodified, so it must not contain any \LaTeX -special characters. The only exception is the semicolon that needs a prefixed backslash, because it would signal the end of the example text otherwise. This must be considered especially for C, C++, and C# examples.

2.2.16 references

The slot `references` (not specified in the `dyn_threshold` example) is used to insert references to literature into the documentation, e.g.,

```
references
  R.M. Haralick, K.G. Shapiro: ``Computer and Robot Vision'\;
  Vol. 1, Addison-Wesley Publishing Company, 1992.;
```

2.2.17 class Information

At the end of the DEF file, i.e., after the parameter section described in the following section, information about the classes generated for HALCON/.NET must be added, in particular the COM class and library IDs in the subslots `iid`, `clsid`, and `libid`. The example below shows the corresponding information in `threshold.def`.

```
class halconuser <- user

short.english
  Sample extension package.;

iid
  {bf6a1001-0b95-11d4-b295-00e0293dc2ac};

clsid
  {bf6a1002-0b95-11d4-b295-00e0293dc2ac};

library halconuser <- user_library

libid
  {bf6a1000-0b95-11d4-b295-00e0293dc2ac};
```

2.3 Describing the Parameters

Please note that the number of parameters is limited for an extension package operators as listed in the Installation Guide, [section 1.5.6](#) on page 13.

Again, the definition of `dyn_threshold` is used as an example. Every description of a single parameter starts with the keyword `parameter` and contains several slots. A slot begins with a characteristic keyword followed by a colon and is finished by a semicolon. All slots specified for the parameters of an operator are accessible online within the HALCON system using the operator `get_param_info`, see the Reference Manuals for details.

```
parameter
  OrigImage:      input_object;
  description.english: Image to be segmented.;
  sem_type:       image;
  type_list:      byte,int2,int4,real;
  multivalued:    optional;

parameter
  ThresholdImage: input_object;
  description.english: Image containing the local thresholds.;
  sem_type:       image;
  type_list:      byte,int2,int4,real;
  multivalued:    optional;

parameter
  RegionDynThresh: output_object;
  description.english: Segmented regions.;
  sem_type:       region;
  multivalued:    optional;
```

```
parameter
  Offset:          input_control;
  description.english: Offset added to ThresholdImage.;
  sem_type:        number;
  type_list:       integer,real;
  default_type:    real;
  default_value:   5.0;
  values:          1.0, 3.0, 5.0, 7.0, 10.0, 20.0, 30.0;
  multivalued:     false;
  assertion:       -255 < Offset && Offset < 255;
  costs_weight:    0;

parameter
  LightDark:       input_control;
  description.english: Extract light, dark or similar areas?;
  sem_type:        string;
  type_list:       string;
  default_type:    string;
  default_value:   light;
  value_list:      dark,light,equal,not_equal;
  multivalued:     false;
  costs_weight:    0;
```

The minimum of information needed for every parameter is its name and type, its default type, its semantic type, the number of values allowed (`multivalued`), and, if the operator should be automatically parallelized, the “costs weight” of input control parameters and the “postprocessing” of output control parameters, see below.

2.3.1 Name

```
parameter
  Name:           input_object,output_object,input_control,output_control;
```

This defines the name and the class of a parameter. The parameters must be described in the same order as in their definition within the header of the operator description.

Note that in order to create PDF hyperlinks referencing parameters (see [section 2.4](#) on page 35 and [section 7.1.4](#) on page 99) a parameter name must consist of alphanumerical characters only!

2.3.2 default_type

```
default_type:          handle, integer,real,string;
```

Only for control parameters! This slot specifies, what C-type to use in general. It must have exactly one of the four above values.

2.3.3 sem_type

```
sem_type:              class[.spec];
```

This slot determines the semantic type, i.e., it specifies the class of data passed as parameters, when using an object-oriented language. Names of classes within the DEF file are only symbolic. The mapping to the actual class names is provided by the HALCON compiler hcomp.

HDevelop also uses the semantic types, e.g., in order to provide specific inspection routines. A list with the semantic types is given in [appendix B](#) on page 141. Some exemplary semantic types (classes) are shown below.

- **Iconic data (object parameters):**

- object (any iconic object: images, regions, XLDs)
- image (images)
- region (regions)
- xld (any XLDs: lines in eXtended Line Description)
- xld_cont, xld_poly, xld_para, xld_mod_para, xld_ext_para

- **Elementary data (control parameters):**

- number (unspecific)
- integer, real, string
- channel (channel number)

- **Handles (control parameters):**

- window (HALCON graphics window)

- **Arrays (control parameters):**

- histogram.values (gray value histogram)
- distribution.values (distribution)

- **Geometric data (control parameters):**

- point.x, point.y (position; (column, row) except for 2D transformations to get mathematically positive rotation)
- extent.x, extent.y (dimensioning)
- angle.deg, angle.rad (angle given in degrees or radians, respectively)
- circle.center.y, circle.center.x, circle.radius (circle)
- line.begin.y, line.begin.x, line.end.y, line.end.x (line)

- `rectangle.origin.y`, `rectangle.origin.x` (rectangle: upper left corner),
`rectangle.corner.y`, `rectangle.corner.x` (lower right corner) or
`rectangle.extent.x` `rectangle.extent.y` (expansion – as alternative to specifying the 2nd corner)
 - `rectangle2.center.y`, `rectangle2.center.x` (rectangle with arbitrary orientation: center),
`rectangle2.angle.rad` (orientation – in radians),
`rectangle2.hwidth`, `rectangle2.hheight` (half the size)
 - `ellipse.center.y`, `ellipse.center.x` (ellipse: center),
`ellipse.angle.rad` (orientation – in radians),
`ellipse.radius1`, `ellipse.radius2` (radii)
 - `arc.center.y`, `arc.center.x` (circle: center),
`arc.angle.rad` (angle stretched by the circular arc – in radians),
`arc.begin.y`, `arc.begin.x` (starting point of circular arc).
 - `hom_mat2d` (2D homogeneous transformation matrix)
`hom_mat3d` (3D homogeneous transformation matrix)
`pose` (3D pose)
- **Numerical region descriptions (control parameters):**
 - `coordinates.y`, `coordinates.x` (coordinates)
 - `contour.y`, `contour.x` (points of a contour)
 - `chord.y`, `chord.x1`, `chord.x2` (runlength code)
 - `polygon.y`, `polygon.x` (polygonal representation)
 - `chain.begin.y`, `chain.begin.x`, `chain.code` (chain code)
 - **Miscellaneous (control parameters):**
 - `filename` (name of a file)
`filename.read` (name of an input file)
`filename.write` (name of an output file)
 - `attribute.name` (name of a generic parameter)
`attribute.value` (value of a generic parameter)

Please note:

- Please *use* the above semantic types for characterizing parameters whenever they are applicable.
- For control parameters characterizing a composed object like a `circle` etc.: Please use the specific *order* of parameters like indicated above.

2.3.4 modified

`modified:` `false,true;`

This slot is used to indicate input parameters that may be modified by the operator, e.g., `handles`. If `modified` is set to 'true', a respective note is automatically created in the corresponding reference manual entry.

2.3.5 multivalued

`multivalued:` `true,false,optional;`

This slot describes the number of values passed in a parameter: 'true' means that an array (tuple) of values must be passed. If 'false' is specified, exactly one value must be passed. 'optional' allows both. If a parameter may also return no values at all, `multivalued` must be set to 'true' or 'optional'.

All slots mentioned so far *must* appear in any extended operator description. Moreover, the following optional slots are recommended to provide further information about parameters:

2.3.6 costs_weight

`costs_weight`: *an unsigned integer value;*

This slot must only be used for input control parameters of operators which are suitable for being automatically parallelized (i.e. for operators for that the `parallelization` subslot method does *not* contain ‘none’; see [page 25](#)). Here, it assigns, whether the time for processing the operator directly depends on the content (value) of the corresponding input control parameter. If `costs_weight` is set to ‘0’, the duration of the operator processing does *not* directly depend on the content of the corresponding input control parameter. In this case, the parameter will *not* be taken into account when HALCON decides, whether an operator should be parallelized for a given allocation of input parameters or not. This also means, that this parameter will not be checked during the hardware training (compare the description of `optimize_aop` in the Reference Manuals). This helps to speed up the training. If `costs_weight` contains a value greater than ‘0’, this assigns that there is a direct dependency between the content of the corresponding input control parameter and the computation time of the operator. In this case, HALCON will take into account this parameter during its hardware check (`optimize_aop`) in order to determine its influence on the operator’s processing time. Note that the slot `costs_weight` *must* be filled in for every input control parameter, if the operator should be automatically parallelized, i.e. if the operator’s slot method does *not* contain ‘none’ (see [page 25](#)).

2.3.7 postprocessing

`postprocessing`: `none,tuple_add,tuple_min,tuple_max,tuple_concat,`
 `channel_add,channel_min,channel_max,channel_concat,`
 `domain_add,domain_min,domain_max,domain_concat;`

This slot must only be used for output control parameters of operators which are suitable for being automatically parallelized (i.e. for operators for that the `parallelization` subslot method does *not* contain ‘none’; see [page 25](#)). Here, `postprocessing` specifies, which kind of postprocessing is used with the single result values of a parallel processed operator. If, for example, an operator is parallelized by splitting a *tuple* of iconic input objects and the single result values of the parallel processed operator must be put into one output control object again, the slot `postprocessing` should contain the keyword ‘`tuple_concat`’ which means “concatenate result values”. Or if an operator is parallelized by splitting the single *channels* of iconic input objects and the overall result value is the minimum of the single result values of the parallel processed operator, `postprocessing` should contain the keyword ‘`channel_minimum`’. Obviously, the slot `postprocessing` can contain several strings in order to define different postprocessing steps for different levels of parallelization (*tuple*, *channel*, and *domain*); of course, there should only be one string per level. If ‘none’ is specified (in this case, no other string should be specified), no postprocessing is done on every parallelization level. This means, that the overall result value of the corresponding output control parameter is directly determined by the result value of the first parallelized operator instance (e.g. the instance which worked on the first tuple element).

Altogether, HALCON currently supports the following postprocessing steps:

- `none`: no postprocessing; adopt first value;
- `tuple_add`: overall result value is the *sum* of the single result values of the tuple parallelization;
- `tuple_min`: overall result value is the *minimum* of the single result values of the tuple parallelization;
- `tuple_max`: overall result value is the *maximum* of the single result values of the tuple parallelization;
- `tuple_concat`: overall result value is a tuple which contains all the result values of the tuple parallelization (“concatenation”);
- `channel_add`: overall result value is the *sum* of the single result values of the channel parallelization;
- `channel_min`: overall result value is the *minimum* of the single result values of the channel parallelization;
- `channel_max`: overall result value is the *maximum* of the single result values of the channel parallelization;
- `channel_concat`: overall result value is a tuple which contains all the result values of the channel parallelization (“concatenation”);
- `domain_add`: overall result value is the *sum* of the single result values of the parallelization on domain level;

- `domain_min`: overall result value is the *minimum* of the single result values of the parallelization on domain level;
- `domain_max`: overall result value is the *maximum* of the single result values of the parallelization on domain level;
- `domain_concat`: overall result value is a tuple which contains all the result values of the parallelization on domain level (“concatenation”);

The example below shows the definition of postprocessing for the operator `circularity`, which calculates the shape factor for the circularity (similarity to a circle) of input regions. If `circularity` is tuple parallelized the overall result is a tuple of values, of which the single elements contain the “circularity” of the single input regions. Thus the postprocessing of the corresponding output control parameter is assigned by ‘`tuple_concat`’.

```
parameter
Circularity:          output_control;
description.english:  Roundness of the input region(s).;
sem_type:             real;
type_list:            real;
default_type:         real;
multivalue:           optional;
assertion:            0 <= Circularity && Circularity <= 1.0;
postprocessing:       tuple_concat;
```

Note that the slot `postprocessing` *must* be filled in for every output control parameter, if the operator should be automatically parallelized, i.e. if the operator’s slot method does *not* contain ‘none’ (see [page 25](#)).

2.3.8 description

```
description.english:    LaTeX/Ascii-Text;
```

This slot contains a short description of the parameter. The extension `.english` refers to a English description. In addition to that a German description might be given in `description.german`. For the syntax of *LaTeX/Ascii-Text* see [section 2.4](#) on page 35.

2.3.9 type_list

The slot `type_list` is only used in connection with object parameters with `sem_type = image` and for control parameters.

For images (`sem_type = image`):

```
type_list:             any,byte,int1,int2,int4,real,cyclic,direction,complex;
```

For images this slot contains an enumeration of all supported pixel types. Note that in many cases there will be more than one supported pixel type. Thus, `type_list` is a list separated by commas.

For control parameters:

```
type_list:             handle, integer,real,string;
```

For control parameters this slot contains a list of all C-types allowed for the parameter.

2.3.10 default_value

```
default_value:         Default;
```

This slot defines the default value e.g., used by HDevelop to initialize the parameter in the operator window. Suggesting default values can help the programmer to find suitable values of parameters. Generally, strings are unquoted in the description (not ‘theString’, but `theString`); exceptions: empty string (‘’) and strings with special characters (‘the string’).

2.3.11 values

values: *Suggested values;*

This slot contains a **collection** of possible values. This list does not have to be *complete*. It just suggests some typical values the user might want to try.

2.3.12 value_list

value_list: *List of values;*

This slot contains a *complete* list of **all** allowed values. So, if a parameter can hold only a discrete number of specific values, `value_list` should be specified, otherwise `values` might be used to provide some typical values.

2.3.13 value_min, value_max

value_min: *Number;*
value_max: *Number;*

Instead of a list an interval may be used to specify a range of values for a parameter. The interval may be unlimited in one direction. The slot `value_min` specifies the minimum of the allowed values, `value_max` the maximum.

Please note that the range is not used to check the passed parameter values. The slots are provided for applications that need the possible range of values to create sliders or other graphical elements to interact with parameters.

To restrict the values of a parameter, please use the slot `assertion` further below.

2.3.14 step_rec, step_min, value_function

step_rec: *Number;*
step_min: *Number;*
value_function: *lin, log, quad, ...;*

If a range of values is possible for a parameter it might be a useful information to specify a suitable step width (`step_rec`) between distinct values to be tested. Based on this information a user interface might generate a list of suggestions for parameter values. The corresponding minimum reasonable step width can be provided by `step_min`. The step width can also be modified by specifying a function in the slot `value_function`.

2.3.15 value_number

value_number: *boolean expression;*

This slot contains a boolean expression that determines how the *number* of passed or returned values of a parameter is absolutely or relatively connected to the number of values in other parameters or some absolute values. The operators and functions listed in [table 2.1](#) may appear within the expression.

Examples:

- `Param1 == Param2 && Param2 > 0`
This means that the same number of values and at least one value must be passed with parameter 1 and parameter 2.
- `Param2 == 3`
This means that exactly three values must be passed with parameter 2.

For output parameters this can be seen as an assertion. This may also refer to input parameters, e.g.: `RegionOut <= RegionIn` in connection with the HALCON operator `select_shape` expresses the fact that the number of output regions does not exceed the number of input regions.

| Group | Symbol | meaning |
|------------------|-----------|---------------------------------------|
| Unary Operators | ! | logical NOT |
| | - | negation |
| Binary Operators | && | logical AND |
| | | logical OR |
| | == | equal |
| | != | not equal |
| | > | greater |
| | >= | greater or equal |
| | < | less |
| | <= | less or equal |
| | + | sum |
| | - | difference |
| | * | multiplication |
| | / | division (DIV) |
| | % | rest of division (MOD) |
| | Functions | odd |
| even | | true, if even |
| ld | | binary logarithm |
| length | | length |
| number | | number of values (only for assertion) |
| width | | (image-)width |
| height | | (image-)height |

Table 2.1: Operators and functions used for the slots `value_number` and `assertion`.

2.3.16 assertion

`assertion:` *boolean expression*;

This slot contains a boolean expression that determines how the passed or returned *values* of parameters are absolutely or relatively connected to the values of other parameters or some absolute values. The same expressions may appear as described above for `value_number`, see [table 2.1](#).

Examples:

- `Param1 == Param2 && Param2 > 0`
This means that parameter 1 and 2 must have the same value and this value is greater than 0.
- `0 <= Param2 && Param2 <= 255`
This means that parameter 2 must have a value between 0 and 255.
- `Param1 <= number(ImageIn)`
This means that the value of parameter 1 must be less or equal the number of input images.
- `Param2 < width(ImageIn) && Param2 >= 0 && odd(Param2)`
This means that the value of parameter 2 must be between 0 and the width of the input image and must be an even number.

2.3.17 multichannel

`multichannel:` `true,false,optional`;

This slot is only used in connections with image objects. It contains an assertion about the necessary or supported number of channels of an image. If set to `false`, the processing is done only on the first channel (all others are ignored), if set to `true`, a multichannel image *must* be passed. `optional` specifies operators that can work on more than one channel but can also work on only one channel as well.

2.3.18 multiinstance

```
multiinstance:      true,false,optional;
```

This slot is used for semantic tuples. A semantic tuple is a tuple of values that, put together, describes a single instance, e.g., a pose (consisting of seven values) or calibration parameters (consisting of several values, depending on the camera type).

The slot `multiinstance` is only used if `multivalues = true`. As for one instance multiple values need to be permitted you can use `multiinstance` in order to specify if multiple semantic tuples may be passed (`true`) or not (`false`). `optional` specifies operators that can work on both one or more semantic tuples.

2.3.19 file_ext, file_ext_descr

```
file_ext:           List of file extensions;
file_ext_descr.english: List of descriptions;
```

These slots are used for parameters of the semantic type `filename` (see [section 2.3.3](#) on page 29). In `file_ext`, you can specify a list of possible file extensions. HDevelop, for example, uses this information when opening file selectors.

In `file_ext_descr.english` (and `file_ext_descr.german`), you can add descriptions for the extensions. If `file_ext` contains a list of extensions, you can either pass a single description for all of them or one for each extension. When passing a list of descriptions, you can insert a period to indicate that the previous value should be used. If a description contains a space, you must enclose it in single quotes. Note that HDevelop automatically appends the text `Files` to the descriptions.

```
Example 1:  file_ext:           tif,tiff,gif;
            file_ext_descr.english: Image;
```

```
results in: Image Files (*.tif; *.tiff; *.gif)
```

```
Example 2:  file_ext:           tif,tiff,gif;
            file_ext_descr.english: 'TIFF Image',.,'GIF Image';
```

```
results in: TIFF Image Files (*.tif)
            TIFF Image Files (*.tiff)
            GIF Image Files (*.gif)
```

2.4 Text in DEF Files

Note that DEF files with non-ASCII characters should be UTF-8 encoded.

Within a DEF file, the semicolon (;) is used to separate the single slots. So, when using a semicolon within a text, it must be quoted with a backslash (\;).

DEF files are not only used to create interface code, but also allow the generation of PDF reference manuals, the HTML documentation, and the help files used to access operator knowledge via HALCON operators like [get_operator_info](#). For the online help and the HTML files an ASCII version of each text is needed, whereas the reference manuals are produced compiling a \LaTeX -file generated from the DEF files. To avoid the necessity of writing two text blocks for one operator (ASCII and \LaTeX), both versions are generated by using one text. Therefore, the following conventions must be observed:

Quotation marks: There are two kinds of quotation marks

'string': This notation signals that the quoted text is a string as used within programming languages. So `hcomp` treats `'string'` as a string-parameter.

“Text”: This notation must be used in all other cases, particularly when quoting a word or text segment because of its content. So `hcomp` treats ```Text''` as a quoted section of a text. Please do not forget or permute the quotation marks (starting with ```` and ending with `''`).

Underscores: Underscores can be used directly for both the ASCII and the \LaTeX output. The HALCON compiler `hcomp` automatically prefixes them with the necessary backslashes for the \LaTeX output (`_.`).

Please note that if you want to use an underscore in a \LaTeX part to create a subscript, you must encase the subscript text in curly braces (`{}`) even if the subscript is only a single character. For example, to create the output `“ S_x ”` you must write `$$_{x}$`. If you leave out the braces, an underscore is printed, e.g., `$$_x$` results in `“ S_x ”`.

Backslash: All backslashes (`\`) within the text are ignored while generating the ASCII version. So the \LaTeX -linefeed-symbol (`\`) can be used without any problems. To embed a literal backslash in the output, use `\textbackslash{}` in the DEF file.

Tilde: To use the tilde (e.g., as symbol for negation: `set_check(::'~clear':)`), the following special notation must be used for the \LaTeX -text: `set_check(::'\~{}clear':)`.

Formulas: Short formulas can be bracketed by dollar symbols (`$`) just as in \LaTeX . These symbols are ignored for the ASCII version of the text.

To set an index of one character (e.g., A_b) \LaTeX allows to simply write `A_b`. This is not possible here, because of the special underscore handling. Therefore, any index must be written exactly as any longer index within \LaTeX : `A_{b}`.

HALCON: The string HALCON is generated by `\Halcon`. Note that in the PDF files derived from the generated \LaTeX version of the DEF files, *no space* is generated after the string HALCON. Thus, if you do not want to start the next character/string without a blank, that is concatenated to the string HALCON, you should use `\Halcon\` instead. So `“\Halcon XYZ”` results in `“HALCON XYZ”` and `“\Halcon\ XYZ”` results in `“HALCON XYZ”`. With the ASCII version all backslashes are ignored (see above).

Names of parameters and operators: Any reference to extension package operators or their parameters must be written as `\OpRef{operator_name}`, respectively as `\ParRef{parameter_name}`. These keywords and the brackets are ignored, when generating the ASCII version so that only *operator_name* or *parameter_name* remains in the ASCII file. In the HTML and PDF documents, hyperlinks are generated from these references.

Parameter values: A specific value for a parameter should be written as `\ValRef{parameter_value}`. For example, the parameter `\ParRef{LightDark}` of the operator `\OpRef{dyn_threshold}` can hold one of the values `\ValRef{'light'}`, `\ValRef{'dark'}`, or `\ValRef{'equal'}`. The keyword `ValRef` and the brackets are ignored, when generating the ASCII version so that only *parameter_value* remains in the ASCII file.

Paragraphs: If you want to divide a longer text into paragraphs to increase the readability, all you need to do is to insert an empty line between the paragraphs:

```
This is a paragraph ...
.. which ends here.
```

```
The next paragraph starts after an empty line ...
```

This corresponds to the standard \LaTeX way of separating paragraphs; in the HTML documents, the paragraphs are enclosed with the tag `<P>`.

Chapter references: You can add a link to a certain chapter or section using `\ChapRef{chapter}` or `\ChapRef{chapter, section}`, respectively. The chapter/section names must match the English names of an existing chapter definition, see [section 2.2.6](#) on page 22.

Formatted text: You can use the following \LaTeX commands to format text both in the \LaTeX and HTML version:

- `\emph{text}`: results in *text* (HTML tag `<E>`)
- `\texttt{text}`: results in `text` (HTML tag `<TT>`)
- `\textbf{text}`: results in **text** (HTML tag ``)
- `\textit{text}`: results in *text* (HTML tag `<I>`)

Please note that these commands cannot be nested!

Links: The following special environment adds a hyperlink to the specified URL into the HTML version of the documentation. In the \LaTeX version, the link text appears as plain text.

```
\begin{External}{URL}
  Link text...
\end{External}
```

Lists: You can use the following \LaTeX environments to format text in lists both in the \LaTeX and HTML version:

description lists:

```
\begin{description}
  \item[title 1] text ...
  \item[title 2] text ...
\end{description}
```

lists with bullet points:

```
\begin{itemize}
  \item text ...
  \item text ...
\end{itemize}
```

enumerated lists:

```
\begin{enumerate}
  \item text ...
  \item text ...
\end{enumerate}
```

Paragraph alignment: You can use the following special environment to specify the alignment of the included text. The parameter format may be set to left, center, or right.

```
\begin{Alignment}{format}
...
\end{Alignment}
```

Tables: You can use the following special environment to format text in tabular format both in the \LaTeX and HTML version. This table environment is not to be confused with the standard \LaTeX table or tabular environment. Tables are centered by default. To change the alignment of a table, enclose it in the Alignment environment (see above).

```
\begin{Table}[style]{format}
  column & column & .. \\
  column & column & ..
\end{Table}
```

Columns are separated by &, and a new row is started with \\. Note that the last row of the table has no trailing \.

The style specification (including the square brackets) is optional. The following values are available:

layout: Simple table without any borders. This is the default if no table style is specified.

grid: Each table cell has a border.

table: The first row is formatted as the table header. The header and the bottom of the table are marked with horizontal lines.

The `format` specification defines the number of columns, their alignment, and (optionally) their width. Each occurrence of one of the letters `l`, `r`, or `c` defines a left-aligned, right-aligned or centered column, respectively. The column specifier may be followed by a number which defines the relative width of the column in percent. Note that the alignment of a column is disregarded in the \LaTeX version if the width is specified. In that case the text of the corresponding column is justified.

For readability, the column specifications may be separated by commas. Extra spacing is ignored. Thus the following table specifications are equivalent:

```
\begin{Table}{l 40, c 30, r 30}
```

```
\begin{Table}{l40c30r30}
```

Other \LaTeX commands: If you want to use additional \LaTeX command within a text segment, two versions of this segment must be provided – one for ASCII (with `@a` signaling the start of the ASCII section) and another as pure \LaTeX text (with `@l` starting the \LaTeX version and `@e` ending the special section). In particular, this technique is necessary for tables and larger formulas.

Example:

```
@a          g_o >= g_m + \ParRef{Offset}
@l\[ g_{o} \ge g_{m} + \ParRef{Offset} \]@e
```

This parenthesis can also be used for only one of the two text types:

```
... text text @l \aSpecialLatexCommand @e text text ...
```

In fact, the ASCII mode has two sub-modes: If `@a` is immediately followed by a carriage return, the following lines are enclosed with the HTML tag `<PRE>`. Thus, they appear “as they come”, including all spaces and carriage returns. Otherwise, i.e., if `@a` is followed by any character (including a space!), carriage returns and spaces are not preserved in the HTML document.

2.5 Chapter Description

Chapters and sections define the structuring of HALCON operators. Sometimes, it is desirable to add an introductory text to a certain chapter or section, e.g., to explain some common concepts of the contained operators.

These chapter descriptions are defined at an arbitrary place in the DEF file outside of an operator description. They are linked to the corresponding chapter using a header that lists the English chapter name, and optionally the English section name:

```
chapter_ref chapter[,section] <- user_chapter
```

The chapter/section names must match the English names of an existing chapter definition, see [section 2.2.6](#) on page 22.

The text of the chapter description is given within the slot `abstract`. It follows the rules of the slot `abstract` used in the operator descriptions. The syntax is explained in [section 2.2.4](#) on page 21.

Thus, a full chapter description looks like this:

```
chapter_ref Filter,Edges <- user_chapter

abstract.english
  Text of the chapter description
  ...
  ;

abstract.german
  ...
  ;

...
```

Again, refer to [section 2.4](#) on page 35 for the special syntax of text.

Chapter 3

Style Guide for Programming

The following chapter contains some recommendations for implementing new HALCON operators. They aim on portable code that should be easy to understand for other HALCON programmers. One of the major topics is the memory management discussed in [section 3.2](#) on page 41.

3.1 Basic Numeric Data Types

This section describes the usage of basic numeric data types. Since C made no assumption about the size of integers prior to the introduction of the C99 standard, HALCON versions 20.11 and earlier define the following types:

| Type Name | C99 Type Name | Size/Range of Values |
|-----------|---------------|---|
| INT1 | int8_t | one byte with sign |
| HBYTE | uint8_t | one byte, unsigned |
| UINT1 | uint8_t | the same as HBYTE |
| INT2 | int16_t | two bytes with sign (generally short) |
| UINT2 | uint16_t | two bytes, unsigned |
| INT4 | int32_t | four bytes with sign |
| UINT4 | uint32_t | four bytes, unsigned |
| INT4_8 | | four (on 32 bit systems) or eight (on 64 bit systems) bytes with sign |
| UINT4_8 | | four (on 32 bit systems) or eight (on 64 bit systems) bytes, unsigned |
| HINT | int | At least two, maximal eight bytes with sign |
| HUINT | unsigned | At least two, maximal eight bytes, unsigned |

Using these types ensures the portability of HALCON operators. If the extension package need not be compilable for HALCON 20.11 or earlier versions, the C99 data types (defined in the `stdint.h` header file) should be used where applicable. Note that C99 does not define any types that exactly match the `INT4_8` or `UINT4_8` types.

3.1.1 Attributes of Iconic Parameters

To use operators in HALCON and HALCON XL, the following types have been introduced. With a compiler define (see [chapter 7](#) on page 97), they are mapped to the suitable basic types for the corresponding image size.

```

#if !defined(HC_LARGE_IMAGES)
typedef int32_t HIMGDIM; /* Image dimension, e.g., width and height */
typedef int16_t HIMGCOORD; /* Image coordinates, e.g, row and column */
typedef int32_t HLINCOORD; /* Linearized image coordinates */
typedef int32_t HIMGCNT; /* Number of pixels, e.g., area or buffer size */
typedef int32_t HITEMCNT; /* Number of elements (contours or runlengths) */
typedef float HSUBCOORD; /* Sub-pixel precise coordinates */
typedef float HSUBATTR; /* Sub-pixel precise attributes of contours */
#else
typedef int32_t HIMGDIM;
typedef int32_t HIMGCOORD;
typedef INT4_8 HLINCOORD;
typedef INT4_8 HIMGCNT;
typedef INT4_8 HITEMCNT;
typedef double HSUBCOORD;
typedef double HSUBATTR;
#endif

```

Examples for their use can be found in [chapter 4](#) on page 49.

3.1.2 Local Variables / Temporary Results

Types and sizes for local variables (no arrays) should be handled as follows:

| Type | Size | C-Data Type |
|-----------------------|--------|--------------------------------|
| Integer | 1 byte | int (HINT) or unsigned (HUINT) |
| | 2 byte | |
| | 3 byte | INT4_8 or UINT4_8 |
| | 4 byte | |
| Floating-point Number | | double |

3.1.3 Procedure Parameters

Parameters of procedures should be of the following types within HALCON:

| Type | Size | C-Data Type |
|-----------------------|--------|-------------|
| Integer | 1 byte | HINT |
| | 2 byte | |
| | 3 byte | INT4_8 |
| | 4 byte | |
| Floating-point Number | | double |
| Structure | | pointer |


3.1.4 Arrays

For arrays or structures (i.e. larger sets) always the smallest possible data type should be used.

| Type | Size | C-Data Type |
|-----------------------|--------|---------------------|
| Integer | 1 byte | int8_t |
| | 2 byte | int16_t or uint16_t |
| | 3 byte | int32_t or uint32_t |
| | 4 byte | |
| Floating-point Number | 4 byte | float |
| | 8 byte | double |
| Structure | | pointer |

3.2 Memory Management

HALCON provides a sophisticated memory management not only to handle iconic objects, but also to allocate/deallocate arbitrary data. Please use the corresponding HALCON Extension Package Interface routines exclusively. Do not create/destroy memory blocks on the heap with the standard routines of the operating system (like `malloc` and `free`) since the HALCON routines provide a caching mechanism, garbage collection for temporary data, and debugging facilities.

We strongly recommend not to use global variables within HALCON operators. If they are not avoidable at least make them `static` within the file of usage. If even this is undesirable group them into structures to keep the number of global names small. 

If you use `static` variables, be aware that they are shared between multiple threads. Please note that HALCON uses multithreading to exploit multi-processor or multi-core hardware. This means, that multiple instances of your code will actually *share* all the static variables! Furthermore, be aware that large static arrays consume a lot of memory – keep in mind that HALCON is a very large system enfolding hundreds of operators.

3.2.1 Temporary Data

Names

`HALlocTmp`, `HFreeTmp`, `HFreeNTmp`, `HFreeUpToTmp`, `HFreeAllTmp`,
`HALlocRLTmp`, `HALlocRLNumTmp`, `HFreeRLTmp`

Synopsis

```
#include "Halcon.h"

Error HALlocTmp(      Hproc_handle proc_handle,
                    void          **pointer,
                    size_t        size)

Error HFreeTmp(      Hproc_handle proc_handle,
                    void          *pointer)

Error HFreeUpToTmp( Hproc_handle proc_handle,
                    void          *pointer)

Error HFreeAllTmp(  Hproc_handle proc_handle)

Error HALlocRLTmp(  Hproc_handle proc_handle,
                    Hrlregion    **region)

Error HALlocRLNumTmp( Hproc_handle proc_handle,
                     Hrlregion    **region,
                     size_t        size)

Error HFreeRLTmp(   Hproc_handle proc_handle,
                    Hrlregion    *region)
```

Figure 3.1: HALCON stack management for temporary data.

Figure 3.1 shows HALCON routines to allocate/deallocate temporary memory blocks. Internally, those blocks are stored within a *stack*. Therefore, the memory *must* be deallocated in reverse order of it's allocation. There are two major advantages of using these routines:

- The underlying stacks are initially allocated as large blocks of memory. Thus, the memory is not fragmented and memory allocation is fast for subsequent calls.
- An automatic garbage collection deallocates all temporary data after a HALCON operator was executed. This is especially of importance in case of an error during the execution of the operator (otherwise, the data should have been deallocated anyway).

HALlocTmp is used for arbitrary data with the corresponding deallocation routine HFreeTmp. HFreeUpToTmp deallocates all recently allocated blocks up to (and including) the specified block. HFreeAllTmp deallocates *all* temporary blocks.

HALlocRLTmp and HALlocRLNumTmp are *convenience* routines that are based on HALlocTmp. HALlocRLTmp allocates as much memory as is necessary for the largest region currently stored in the HALCON database of iconic objects (the minimal size is DEF_RL_LENGTH = 50000 chords). Using HIncrRL (section 5.6.5 on page 84), HALlocRLTmp allocates more memory. HALlocRLNumTmp allows you to determine the size of memory to be allocated by specifying the number of chords. Furthermore, HALlocRLTmp and HALlocRLNumTmp initialize the data structure Hrlregion for the new region (see section 4.2 on page 50 for a description of Hrlregion). Note that since these routines are based on HALlocTmp the corresponding memory blocks are interleaved with the blocks allocated directly via HALlocTmp. This has to be considered while deallocating the corresponding memory.

Temporary data on arbitrary heap positions

Names

```
HALlocLocal, HReallocLocal, HFreeLocal,
HALlocRLLocal, HALlocRLNumLocal, HReallocRLNumLocal, HFreeRLLocal
```

Synopsis

```
#include "Halcon.h"

Error HALlocLocal(      Hproc_handle proc_handle,
                       size_t      size,
                       void        **pointer)

Error HReallocLocal(   Hproc_handle proc_handle,
                       void        *pointer
                       size_t      size,
                       void        **new_pointer)

Error HFreeLocal(     Hproc_handle proc_handle,
                       void        *pointer)

Error HALlocRLLocal(  Hproc_handle proc_handle,
                       Hrlregion   **region)

Error HALlocRLNumLocal( Hproc_handle proc_handle,
                       Hrlregion   **region,
                       size_t      num)

Error HReallocRLNumLocal( Hproc_handle proc_handle,
                           Hrlregion   *region
                           size_t      num_new,
                           Hrlregion   **new_region)

Error HFreeRLLocal(   Hproc_handle proc_handle,
                       Hrlregion   *region)
```

Figure 3.2: Temporary data on arbitrary heap positions.

The temporary data management routines described so far use a stack. This is of advantage concerning runtime, but it lacks flexibility if you do not want to deallocate memory in a fixed order again. Therefore, HALCON also provides routines for allocating temporary memory on an arbitrary position of the heap, see figure 3.2. Memory blocks allocated by HALlocLocal can be deallocated by HFreeLocal in an arbitrary order. However, similar to the stack-based temporary data management, all these blocks are automatically deallocated at the end of a HALCON operator. Again this mainly aims on preventing memory leaks in case of errors. As usual, the routine HReallocLocal is used to allocate a new memory block with modified size while preserving the data of the original memory block. The latter is deallocated. So *never* try to access pointer subsequent to HReallocLocal-use new_pointer exclusively.


The convenience routines `HALlocRLLocal`, `HALlocRLNumLocal`, `HReallocRLNumLocal`, and `HFreeRLLocal` are used for handling temporary region data based on `HALlocLocal`. Otherwise their behavior is similar to `HALlocRLTmp` etc., see above. E.g., using `HIncrRL` (section 5.6.5 on page 84), `HALlocRLLocal` allocates more memory. However, note that it is possible to *change* the size of regions (i.e., the number of chords) using this set of routines (`HReallocRLNumLocal`) since the underlying memory blocks are not allocated within the internal stacks.

Handle Data

| <u>Name</u> | | |
|----------------------------------|----------------------------------|--|
| <code>HALlocOutputHandle</code> | | |
| <u>Synopsis</u> | | |
| <code>#include "Halcon.h"</code> | | |
| <code>Error</code> | <code>HALlocOutputHandle(</code> | <code>Hproc_handle</code> <code>proc_handle,</code> |
| | | <code>int</code> <code>par,</code> |
| | | <code>Hphandle</code> <code>elem,</code> |
| | | <code>H_HANDLE_TYPE</code> <code>HHandleInfo)</code> |

Figure 3.3: Memory management for handles.

The routine `HALlocOutputHandle` allocates one handle in the output control parameter `par`. `HHandleInfo` holds handle type information. `elem` is modified to point to where the new tool can be allocated.

The output control variable gains ownership of the pointer in `elem`. When aborting an operator with an error, the value must not be cleared inside the operator's code, but will be cleared automatically when cleaning the output control variable. 

3.2.2 Permanent Data

The HALCON Extension Package Interface also provides routines for permanently allocating/deallocating memory (see figures 3.4 and 3.5). They work similar to the standard C procedures `malloc` and `free`, but use a caching mechanism for small data blocks and provide additional debugging information.

Note that in contrast to `HALlocLocal`, memory allocated by `HALloc` is not deallocated automatically after the execution of a HALCON operator. Thus, this routine should be used to allocate permanent data. For example, all the iconic objects stored in the HALCON database of iconic objects are allocated with this routine (see chapter 5 on page 57 and chapter 6 on page 87).

`HNewImage` allocates raw image data inside¹ the data structure `Himage` (see section 4.1 on page 49) based on `HALloc`. Furthermore, `image` is initialized and the timestamp is set to the current time. The image matrix itself is initialized with 0 if `'init_new_image'` has been set to `'true'` using the HALCON operator `set_system`. This flag can be *read* inside HALCON using the Extension Package Interface call `HReadGV`.

```
HReadGV(proc_handle, HGInitNewImage, &init_new_img);
```

with `init_new_img` of type `bool` and *set*

```
HWriteGV(proc_handle, HGInitNewImage, {true,false});
```

Thus, it is possible to buffer the global setting of this flag, set the flag to `false` prior to `HNewImage`, and restore the old value afterward, if you would like to prevent an initialization in any case.

`HNewImagePtr` does not allocate memory for the image data, but inserts the pointer data in the `Himage` structure `image` instead. For this routine, the initialization of the image data is controlled via the parameter `initImg`. Note

¹So `HNewImage` does not allocate memory for the `Himage` structure itself.

Names

```
HAlloc, HRealloc, HFree, HNewImage, HNewImagePtr,
HAllocXLDCont, HFreeXLDCont
```

Synopsis

```
#include "Halcon.h"

Error HAlloc(      Hproc_handle proc_handle,
                  size_t      size,
                  void        **pointer)

Error HRealloc(   Hproc_handle proc_handle,
                  void        *pointer
                  size_t      size,
                  void        **new_pointer)

Error HFree(      Hproc_handle proc_handle,
                  void        *pointer)

Error HNewImage(  Hproc_handle proc_handle,
                  Himage      *image,
                  int          kind,
                  HIMGDIM     width,
                  HIMGDIM     height)

Error HNewImagePtr( Hproc_handle proc_handle,
                   Himage      *image,
                   int          kind,
                   HIMGDIM     width,
                   HIMGDIM     height,
                   void        *data,
                   bool        initImg)

Error HAllocXLDCont( Hproc_handle proc_handle,
                   Hcont        **cont,
                   HITEMCNT     num_points)

Error HFreeXLDCont( Hproc_handle proc_handle,
                   Hcont        *cont)
```

Figure 3.4: General memory management within HALCON.

that you will encounter program crashes during deallocation of image objects, if you insert a memory block that has not been allocated via `HAlloc` in the underlying `Himage` structure (see, e.g., `HPutImage` in [section 5.4](#) on page 67).

For both `HNewImage` and `HNewImagePtr` the pixel type of the raw data within `image` is specified by the parameter `kind`. Please see [figure 4.2](#) on page 50 for the supported values.

`HAllocXLDCont` allocates an XLD contour² of type `Hcont` (see [section 4.3](#) on page 52) including memory for `num_points` contour points. Internally this routine is based on `HAlloc`. `HFreeXLDCont` is used to deallocate a contour again (including all the points *and* all attributes defined for `cont`, see [page 54](#)).

The convenience routines `HAllocRL`, `HAllocRLNum`, `HReallocRLNum`, and `HFreeRL` (see [figure 3.5](#)) are used for handling permanent region data based on `HAlloc`. Otherwise, their behavior is similar to `HAllocRLTmp` etc. E.g., using `HIncrRL` ([section 5.6.5](#) on page 84), `HAllocRL` allocates more memory, see [page 42](#). Note that it is possible to *change* the size of regions (i.e., the number of chords) using `HReallocRLNum`.

²In contrast to `HNewImage` and `HNewImagePtr` `HAllocXLDCont` also allocates memory for the structure `Hcont` itself, not only for the data inside that structure.

Names

```
HALlocRL, HALlocRLNum, HReallocRLNum, HFreeRL
```

Synopsis

```
#include "Halcon.h"

Herror HALlocRL(      Hproc_handle proc_handle,
                    Hrlregion  **region)

Herror HALlocRLNum(  Hproc_handle proc_handle,
                    Hrlregion  **region,
                    size_t      len)

Herror HReallocRLNum( Hproc_handle proc_handle,
                    Hrlregion  *region,
                    size_t      len,
                    Hrlregion  **new_region)

Herror HFreeRL(      Hproc_handle proc_handle,
                    Hrlregion  *region)
```

Figure 3.5: General memory management for region data.

3.2.3 Debugging

The HALCON memory management provides debugging mechanisms. The debugging is enabled with `set_check('memory')`, and can be switched off with `set_check('~memory')`. Every time a memory block is deallocated a couple of consistency checks are performed automatically. Moreover, the consistency of memory blocks can be checked for debugging reasons at any time using specific Extension Package Interface routines, see [figure 3.6](#).

Names

```
HTestMem, HTestPtr, HTestAllTmp, HTestTmp
```

Synopsis

```
#include "Halcon.h"

Herror HTestMem(      void)

Herror HTestPtr(      void      *pointer)

Herror HTestAllTmp(  Hproc_handle proc_handle)

Herror HTestTmp(      Hproc_handle proc_handle,
                    void      *pointer)
```

Figure 3.6: HALCON memory management: Check of consistency.

`HTestMem` checks all the memory allocated with `HALloc` or `HALlocLocal`, whereas `HTestPtr` checks only the specified memory block, which must have been allocated with `HALloc`. Similar to that, `HTestAllTmp` checks all the memory allocated via `HALlocTmp`, and `HTestTmp` checks the specified block. With any failure of the consistency check, the routines return an error code (`H_ERR_ICM` – inconsistent memory). Furthermore, if the global variable `HDoLowError` is set to `true`, they display a description of the error either on `stderr` (Unix-like systems) or within an alert box (Windows). This variable can be set in an application with the operator `set_system("do_low_error", "true"/"false")` or used directly inside the newly written operator.

3.3 Structuring Programs

HALCON operators are typically implemented by at least two routines: one procedure (supply procedure) receives/unpacks all input data and checks its consistency. Afterward, it calls the action procedure, which performs the image processing. In some cases, it can be convenient to implement several action procedures dependent on special parameter values or pixel types of image data. Generally, these steps are performed within a loop over all input iconic objects that may include further loops over different parameter values and over all image channels. The results are collected and finally returned to the HALCON interface to the application.

Supply procedures are of type `Herror` and have only one parameter (a handle of type `Hproc_handle` for instances of HALCON operators or HALCON threads). Do not forget to return an appropriate value at the end of every supply procedure (standard value: `H_MSG_TRUE`) and every action procedure (standard value: `H_MSG_OK`).

Typically, action procedures perform the image processing itself. They should return an error code of type `Herror` as well. It is convenient to implement an action procedure for each pixel type of image data.

3.4 Extension Package Initialization

To initialize an extension package, the following optional function may be defined:

```
extern HUserExport Herror HXPkgMain(Hproc_handle)
```

If defined, HALCON will call this function upon loading the extension package. For example, this mechanism is useful to initialize synchronization objects (e.g., mutexes) that will be used in the extension package.

3.5 Name Conventions for Procedures

To ease the interpretation of program code, HALCON introduces some conventions for procedure names. The most important ones are summarized in the following section.

The names of action procedures typically begin with “IP” (image processing procedure), “IO” (input/output procedure), or “DB” (data base procedure). The rest of the name describes the task performed by the procedure (in English language, beginning with a capital letter). In case of filters an additional token might be inserted between these two parts of the name encoding the pixel type(s) of images to be processed, e.g., “B” (HBYTE), “I4” (INT4) or “F” (float).

Examples:

```
IPBLowpas
IPI4Threshold
IODispRegion
DBGetTuple
```

Basic routines performing a small task that might be used by many other routines should start with “H” (for *Help*). The leading “H” should be followed by a string encoding the data the routine works on, e.g., “RL” for an auxiliary routine processing region data, or “XLD” for routines working on XLDs.

Examples:

```
HRLUnion
HXLDContLen
HXLDContRegress
```

Names of supply procedures start with “C” (this stands for *Core*). The rest is determined by the name of the underlying action procedure (if there is only one). If there are several action procedures with names differing only by the symbols for different pixel types, the pixel type is left out in the name of the supply procedure.

Examples:

```
CIPLowpas
CIPThreshold
CIOOpenWindow
```

3.6 Input / Output

Except explicit IO routines HALCON procedures should not contain any input/output commands, especially no print commands. Any interaction should be done either via parameters or via Extension Package Interface in-/output procedures. Error messages should be encoded by proper error code returned by the procedure (see next section).

3.7 Error Handling

3.7.1 Defining Own Error Codes

Error messages are represented by integer constants, the error codes of type `Error`. If an error occurs, the corresponding error code should be returned by the procedure.

The file `%HALCONROOT%\include\HErrorDef.h` contains predefined error messages for all typical errors, see also [appendix A](#) on page 105. But it may happen that none of them fits an error occurring in a new, user-defined operator. So the user is allowed to define new codes that should be greater than 10 000 to avoid re-using an already allocated code or a code reserved for future extensions of the HALCON system. If the user-defined operator returns a user-defined error, the error will be reported as

No error message available for this error code (<error code>).

In order to provide user-defined errors with error messages, the function `HSetErrText`

```
Error HSetErrText(char *error_message)
```

can be called immediately before the operator returns the error code with `return H_ERR_*`. In this case the error message `error_message` will be displayed by the *next*³ call of the HALCON operator `get_error_text`.

Error codes are specified via `#define` and are called `H_ERR_XYZ`.

Examples:

```
H_ERR_WIPN1 /* wrong number of values in input control */
            /* parameter 1 */
H_ERR_WIPV3 /* wrong parameter value (control param. 3) */
H_ERR_WIPT2 /* wrong type of values (control param. 2) */
H_ERR_WION1 /* wrong number of objects in input object */
            /* parameter 1 */
H_ERR_WIT   /* wrong image type */
H_MSG_TRUE  /* no error (supply procedure) */
H_MSG_OK    /* no error (any other procedure) */
```

All HALCON procedures return an error code. This code has to be checked after calling any HALCON procedure, e.g., by encapsulating the procedure call in the macro `HChkP`. This macro checks the return value and exits the current procedure if an error occurred (a detailed description of the macro is given in the [section 5.6.1](#) on page 83). Please note that some of the Extension Package Interface macros described in [chapter 5](#) on page 57 and [chapter 6](#) on page 87 (e.g., `HGetCPar`) implicitly use the macro and therefore automatically return a proper error code.

3.7.2 Extending Error Codes

There is also a mechanism to add some extended error information about the thread's current HALCON error. The function `HSetExtendedErrorInfo`

```
Error HSetExtendedErrorInfo(Hproc_handle proc_handle, INT4_8 error_code,
                           char const *error_message)
```

³Within this call the error message is reset to "No error message available ..." again to ensure that the user-defined error message is up to date.

can be called immediately before the operator returns the error code with `return H_ERR_*`. In this case the extended error information (`error_code` and `error_message`) will be set thread-locally and can be queried by the next call of the HALCON operator `get_extended_error_info`. The set information gets cleared by both the next occurring HALCON error or the next call of `HSetExtendedErrorInfo`.

In `error_code`, a user-defined error code can be set, e.g., a 3rd Party SDK error code or a 0 value (indicating that no extended error code is set).

In `error_message`, a user-defined error message can be specified, e.g., a 3rd Party SDK error message or an empty string "" (indicating that no extended error message is set).

An example of how to use `HSetExtendedErrorInfo` is provided in `$HALCONEXAMPLES/extension_package/useropencl/source/CIPOpenCLFilter.c`. An example of how to obtain the extended error information by means of `get_extended_error_info` is provided in `$HALCONEXAMPLES/extension_package/useropencl/examples/testuseropencl.hdev`.

3.8 Notes on Image Processing Operators

- HALCON images are variable in their size (format). Therefore, no constants should be used for image formats (except `MAX_FORMAT` for the maximum format). The actual format of an image can be extracted from the structure `Himage` (cf. [figure 4.1](#) on page 50).
- Notice that more than one pixel type may occur, when performing gray value operations. An operator should be able to work on all of them, see also the discussion in [section 6.1.3](#) on page 90. If an operator can only process a reduced set of types, this can be specified in the DEF file with `type_list` (cf. [page 32](#)). An operator should reject all images that it can not process by returning `H_ERR_WIT` – wrong image type.
- In many cases an operator might receive more than one iconic object as input, i.e. the supply procedure must contain a loop over all iconic objects (e.g., using `HAllReg` and `HAllSegm` described in [section 6.1](#) on page 87 or `HAllObj` in [section 5.3.1](#) on page 66). This is true for regions as well as images or XLDs. Furthermore, images may contain more than one channel. So a second loop over all channels (components) within an image is needed (see `HAllComp`, [section 5.3.2](#) on page 66).
- All procedures should only work within the image's area of definition, especially when performing feature extraction, filter or segmentation tasks.

Chapter 4

HALCON Data Types

The HALCON Extension Package Interface provides special data types to handle iconic objects. All iconic objects in the application layer are represented by a key referring to the HALCON database of iconic objects. The internal structure is hidden from the HALCON user. However, using the Extension Package Interface it is possible to work directly on the data structures for images, regions, and XLDs. Special macros can be used to access the internal representation of such an iconic object. Furthermore, data structures for control parameters are provided. All data types described in the following sections are defined in the files `%HALCONROOT%\include\IType.h` and `%HALCONROOT%\include\HBase.h`.

4.1 Pixel Data (Himage)

Gray value images are represented by a rectangular image matrix. Several matrices (called *channels*) can be combined to a multi-channel image. Each channel can be accessed separately, i.e. the channels are not interleaved. The structure `Himage` contains size, pixel type, and pixel data of one channel. Furthermore, a time-stamp is included. [Figure 4.1](#) shows the corresponding type declaration.

The maximum for `width` and `height`, which describe the image size, is determined with `MAX_FORMAT` (HALCON: 32 768, HALCON XL: 1 073 741 824). The origin of an image matrix is at position (0, 0). Row coordinates range from 0 to `height - 1`, column coordinates from 0 to `width - 1`. The image pointer (`HPixelImage`) refers to the first pixel of the matrix (index: 0,0). Different pixel types are supported. They are distinguished by a selector (`kind`), see [figure 4.2](#). The pixel types include basic types like `uint8_t`, `int8_t`, `int32_t`, and `float` as well as composed types. Their definitions can be seen in [figure 4.3](#).

The pixel data is stored as a one-dimensional array (image vector) of one of the pixel types. The indices of the array range from 0 to `width*height-1`. A linear coordinate `L` within an image is derived from the row index `R` and column index `C` as follows:

$$L = R * \text{image.width} + C$$

This transformation is performed by the following macro `HLinCoord`:

```
L = HLinCoord(R,C,image.width);
```

There are two additional macros for computing rows (`HRow`) and columns (`HCol`):

```
R = HRow(L,image.width);  
C = HCol(L,image.width);
```

Please see [section 3.2.2](#) on page 43 for routines to allocate image data within `Himage`.

```

typedef union {
  uint8_t*    b;          /* 0..255 (BYTE_IMAGE)          */
  uint8_t*    z;          /* 0..255 mod 256 (CYCLIC_IMAGE) */
  uint8_t*    d;          /* orientation 0..180 (DIR_IMAGE) */
  int8_t*     i;          /* -128..127 (INT1_IMAGE)       */
  int32_t*    l;          /* 4 byte integer (LONG_IMAGE)   */
  int64_t*    i8;         /* 8 byte integer (INT8_IMAGE)   */
  float*      f;          /* 4 byte real (FLOAT_IMAGE)     */
  HVFPixel*   vf;         /* vector field (VF_IMAGE)       */
  HComplexPixel* c;       /* complex image (COMPLEX_IMAGE) */
  HInt2Pixel  s;          /* 2 bytes with sign (INT2_IMAGE) */
  HUInt2Pixel u;          /* 2 bytes without sign (UINT2_IMAGE) */
} HPixelFormat;

typedef struct {
  int          kind;       /* pixel type                    */
  HPixelFormat pixel;     /* pixel data                    */
  HIMGDIM     width;      /* image width                   */
  HIMGDIM     height;     /* image height                  */
  HImageFreeProc free_proc; /* function for deallocating image data */
  bool        free;       /* free image data when deleting image */
  /* time of creation of image */
  uint16_t    msec;       /* milliseconds 0..999          */
  uint8_t     sec;        /* seconds 0..59                */
  uint8_t     min;        /* minutes 0..59                */
  uint8_t     hour;       /* 0..23                         */
  uint8_t     day;        /* 1..31                         */
  uint16_t    yday;       /* 1..366                       */
  uint8_t     mon;        /* 1..12                         */
  uint16_t    year;       /* 19xx                          */
} HImage;

```

Figure 4.1: Data type Himage for images.

```

#define BYTE_IMAGE      (int)1    /* 1 byte per pixel (0..255)    */
#define INT4_IMAGE      (int)2    /* Type: 4 bytes per pixel (int32_t) */
#define LONG_IMAGE      (int)2    /* 4 byte per pixel (int32_t)    */
#define FLOAT_IMAGE     (int)4    /* 4 byte per pixel (float)      */
#define DIR_IMAGE       (int)8    /* edge orientation 0..180      */
#define CYCLIC_IMAGE    (int)16   /* 0..255 cyclic                 */
#define INT1_IMAGE      (int)32   /* -128..127                    */
#define COMPLEX_IMAGE   (int)128  /* 2 float images               */
#define INT2_IMAGE      (int)512  /* 2 bytes with sign            */
#define UINT2_IMAGE     (int)1024 /* Type: 2 bytes (unsigned short) */
#define VF_IMAGE        (int)2048 /* Two float images             */
#define INT8_IMAGE      (int)4096 /* 8 byte per pixel (int64_t)    */

```

Figure 4.2: Definitions of pixel types.

4.2 Region Data (Hrlregion)

In HALCON region data is represented by a special variant of the *runlength encoding* – a *chord encoding*: For every line (chord) of a region its row index (“y coordinate”, “line number”) and the column index (“x coordinate”) of its start and end point is stored. Both the start point and the end point belong to the region.

Chord data must fulfill the following conditions:

- a chord is limited to one row
- chords may not overlap

```

typedef struct {
    float re;           /* real image part      */
    float im;           /* imaginary image part */
} HComplexPixel;

typedef struct {
    int16_t* p;         /* gray values          */
    int8_t  num_bits;  /* number of used bits  */
} HInt2Pixel;

typedef struct {
    uint16_t* p;        /* gray values          */
    int8_t  num_bits;  /* number of used bits  */
} HUInt2Pixel;

typedef struct {
    float* row;         /* row direction        */
    float* col;         /* column direction     */
} HVFPixel;

```

Figure 4.3: Data types for Himage.

- chords are sorted in ascending order

If a region is read from the HALCON database of iconic objects, its representation fulfills all the conditions above. When writing a region, condition 2 and 3 need not to be sufficed in all cases, as the Extension Package Interface automatically modifies the data (at cost of computation time).

```

typedef struct {
    HIMGCOORD l;        /* line number (row) of run          */
    HIMGCOORD cb;       /* column index of beginning of run  */
    HIMGCOORD ce;       /* column index of ending of run     */
} Hrun;

typedef struct {
    bool    is_compl;   /* region is complement              */
    HITEMCNT num;       /* number of runs                    */
    HITEMCNT num_max;   /* maximum number of runs            */
    HRegFeature feature; /* already processed features        */
    Hrun*   rl;         /* pointer on array of run lengths    */
} Hrlregion;

```

Figure 4.4: Data type Hrlregion for region encoding.

Figure 4.4 shows the type declaration for chords. In the structure `Hrlregion`, all chords are stored in an array of the type `Hrun`, where `num` is the current and `num_max` the maximum allowed number of chords (depending on the size of the region specified at its creation, see also [section 3.2](#) on page 41). The flag `is_compl` allows an easy transformation of a region in its complement. Operators that work on regions must consider this flag and react according to its value. The structure `HRegFeature` (see [figure 4.5](#)) contains all region shape features extracted so far to avoid repeating a computation. `HFeatureFlags` encodes, which features already have been extracted. Do not forget to reset these flags if you modify a region.

Normally, a variable of type `Hrlregion` is allocated with the procedure `HAllocRLTmp` or `HAllocRLNumTmp`, see [section 3.2](#) on page 41. These routines initialize the data, especially `num_max` that is needed for tests of overflow. When allocating a variable “by hand”, the programmer must provide a suitable initialization by himself/herself.

Whereas all coordinates within `runlength` codes are stored as (row,column), linear coordinates are used to address HALCON image matrices. Thus, the macros `CB` and `CE` are very helpful, especially when processing gray values (in linear coordinates) along a chord. The programs in [figure 6.5](#) on page 91 and [figure 6.7](#) on page 93 illustrate how to use them. Their functionality can be seen in [figure 4.6](#). The first parameter (`rl`) contains a pointer to the chords as it is used within `Hrlregion`. `index` specifies the index of the chord to work on and `width` contains the image width. `CB` returns the linear coordinate of the start point and `CE` that of the end point of the chord.

```

typedef struct {
  union {
    HFeatureFlags single;
    long all; /* if possible use 64 bits! */
  } def;
  uint8_t shape; /* SHAPE_*
  bool is_convex;
  bool is_filled;
  bool is_connected4;
  bool is_connected8;
  bool is_thin; /* one pixel thin
  double circularity;
  double compactness;
  double contlength;
  double convexity;
  double phi;
  double ra, rb; /* elliptic_axis
  double ra_, rb_; /* elliptic_shape
  double anisometry, bulkiness, structure_factor;
  double m11, m20, m02, ia, ib;
  double row, col;
  HIMGCNT area;
  HIMGCOORD row1, col1, row2, col2;
  double row_rect, col_rect, phi_rect, length1, length2;
  double row_circle, col_circle, radius;
  HIMGCOORD min_chord, max_chord;
  HIMGCOORD min_chord_gap, max_chord_gap;
  double rectangularity;
} HRegFeature;

```

Figure 4.5: Data type HRegFeature for region shape features.

Names

CB, CE

Synopsis

#include "Halcon.h"

```

HLINCOORD CB(Hrun* rl,
             HITEMCNT index,
             HIMGDIM width)

```

```

HLINCOORD CE(Hrun* rl,
             HITEMCNT index,
             HIMGDIM width)

```

Figure 4.6: Linear coordinates from Hrlregion.

4.3 XLDs (Hcont, Hpoly)

XLDs (eXtended Line Descriptions) are specific iconic HALCON objects to represent subpixel accurate contours and polygons. The corresponding data types Hcont and Hpoly are listed in [figures 4.7](#) and [4.8](#).

HALCON contours of type Hcont contain an array of subpixel points along a contour. A contour might be classified concerning to topological considerations (cont_class). Additionally, an arbitrary number of additional contour attributes for each point along the contour can be included (attribs), e.g., the edge amplitude of subpixel edge points or the orientation of the local gradient. Finally, an arbitrary number of additional global attributes, i.e., attributes valid for the entire contour, can be included (global), e.g., the individual parameters of a regression line to the contour or the parameters of an ellipse segment fitted to the contour.

```

typedef enum cont_class {
    cont_unknown,          /* unknown */
    cont_no_junc,         /* neither start nor end point points
                          /* are junctions */
    cont_start_junc,     /* start point is a junction */
    cont_end_junc,       /* end point is a junction */
    cont_both_junc,     /* both start and end point are junctions */
    cont_closed          /* closed contour */
} Hcont_class;

typedef struct cont_attrib {
    char      *name;      /* name of the attribute */
    HSUBATTR  *val;       /* value of the attribute (per point) */
} Hcont_attrib;

typedef struct cont_global_attrib {
    char      *name;      /* name of the global attribute */
    HSUBATTR  val;        /* value of the attribute (per contour) */
} Hcont_global_attrib;

typedef struct cont_type {
    HITEMCNT  num;        /* number of points along the contour */
    HSUBCOORD* row;       /* points / row indices (y coordinates) */
    HSUBCOORD* col;      /* points / column indices (x coord.) */
    Hcont_class cont_class; /* contour class */
    int32_t   num_attrib; /* number of additional attributes */
    Hcont_attrib* attribs; /* additional attributes (for each point) */
    int32_t   num_global; /* number of additional global attributes */
    Hcont_global_attrib* global; /* additional attributes (per contour) */
    int32_t   h;         /* auxiliary (temporary) */
} Hcont;

```

Figure 4.7: The XLD data type Hcont for subpixel contours.

```

typedef struct lin_seg_type {
    HSUBCOORD  row,col; /* a control point of the polygon:
                       /* row (y) and column (x) coordinate */
    HSUBATTR   length;  /* length of the line from the
                       /* current to the next point */
    HSUBATTR   phi;     /* orientation (rad) of this line */
    Hkey       ref;     /* database key of the underlying
                       /* contour */
    HITEMCNT   first;   /* index of the first point of the
                       /* underlying contour belonging to
                       /* current side of the polygon */
    HITEMCNT   last;   /* index of the last contour point */
} Hline_seg;

typedef struct poly_type {
    HITEMCNT  num_line; /* number of lines */
    HITEMCNT  len_line; /* maximum number of lines (size
                       /* of the array lines) */
    Hline_seg* lines;   /* control points of the polygon */
} Hpoly;

```

Figure 4.8: The XLD data type Hpoly for subpixel polygons.

Please see [section 3.2.2](#) on page 43 for routines to allocate/deallocate contours. Two important auxiliary routines to copy contours are listed in [figure 4.9](#) on page 54. HCopyXLDCont copies a complete contour, whereas HCopyXLDContPart copies only a part of the original contours specified by two indices min_index and max_index. They refer to the first and the last point along the contour to be copied (starting with index 0).

Names

HCopyXLDCont, HCopyXLDContPart

Synopsis

```
#include "Halcon.h"
```

```
Errorr HCopyXLDCont(      Hproc_handle proc_handle,
                          Hcont*      cont_in,
                          bool         preserve_attribs,
                          bool         preserve_global_attribs,
                          Hcont**     cont_out)
```

```
Errorr HCopyXLDContPart( Hproc_handle proc_handle,
                          Hcont*      cont_in,
                          INT4_8     min_index,
                          INT4_8     max_index,
                          bool         preserve_attribs,
                          bool         preserve_global_attribs,
                          Hcont**     cont_out)
```

Figure 4.9: Auxiliary routines for contours of type Hcont.

Names

HAddXLDContAttrib, HLookupXLDContAttrib,
HAddXLDContGlobalAttrib, HLookupXLDContGlobalAttrib

Synopsis

```
#include "Halcon.h"
```

```
HAddXLDContAttrib(      Hproc_handle proc_handle,
                          Hcont*      cont,
                          char*       name,
                          int32_t*    index)
```

```
HLookupXLDContAttrib(  Hcont*      cont,
                          char*       name,
                          int32_t*    index)
```

```
HAddXLDContGlobalAttrib( Hproc_handle proc_handle,
                          Hcont*      cont,
                          char*       name,
                          int32_t*    indx);
```

```
HLookupXLDContGlobalAttrib( Hcont*      cont,
                              char*       name,
                              int32_t*    indx);
```

Figure 4.10: Handling contour attributes of contour pixels (within Hcont).

For closed contours a negative value might be specified for `min_index`. This will lead to a “wrap-around”, that is the part of the contour to be copied starts at `cont_in->num + min_index`. Both `HCopyXLDCont` and `HCopyXLDContPart` allocate the output contour *themselves*. So just pass a *pointer to a pointer* to `Hcont` without allocating any memory for `cont_out`. Both routines provide two additional parameters, `preserve_attribs` and `preserve_global_attribs`, to control whether the non-global and the global contour attributes should be copied.

The routines provided for handling contour attributes of contour points are summarized in [figure 4.10](#). `HAddXLDContAttrib` is used to add a new class of contour attributes to a given contour `cont`. Note that this routine allocates memory for the attribute values, but it does not set the values themselves. An arbitrary name for

the attribute can be specified by the parameter name. The index of the new attribute within the `attrs` array in `cont` is returned in `index` and can be used to address the values by `cont->attrs[index].val[xxx]`. The same holds for global attributes: `HAddXLDContGlobalAttrib` is used to add new global attributes, which can be accessed by `cont->global[index].val`. Note that these values can be accessed within the HALCON system (that is on the application layer) using the operators `get_contour_attrib_xld` and `get_contour_global_attrib_xld`. See the Reference Manuals for details. Within HALCON, a specific attribute of a contour can be accessed using `HLookupXLDContAttrib`, while a specific global attribute can be accessed using `HLookupXLDContGlobalAttrib`. These routines return the index of the desired attribute within `attrs` or `global` of `cont`, or the error code `H_ERR_XLD_CAND` as result of the procedure call, if no attribute with the specified name is defined.

The XLD data type `Hpoly`, displayed in [figure 4.8](#) on page 53, encodes subpixel accurate polygons. Basically it contains an array of control points. In many applications such polygons are derived from contours. Thus, the data structure can also hold a reference to the underlying part of a contour specified by a HALCON database key.

4.4 Control Parameters

```
typedef union {
    INT4_8  l;    /* 4/8 byte integer */
    double  d;    /* 8 byte real */
    char*   s;    /* string */
    Hhandle H;   /* Pointer to handle */
} Hpar;

typedef struct {
    Hpar par;
    int  type;
} Hcpar;
```

Figure 4.11: Data types `Hpar` and `Hcpar` for control parameters.

HALCON's basic and essential view on control data are arrays. These arrays are used to pass control parameter values to supply procedures and can assume five different types, four basic or a mixed type, see [section 2.3](#) on page 28.

Basic types are supported `INT4_8` arrays, coded as `LONG_PAR`, double arrays coded as `DOUBLE_PAR`, handle arrays coded as `HANDLE_PAR`, and string arrays, i.e., `char*` arrays, coded as `STRING_PAR`. Note that all strings passed to and from the HALCON library must be encoded in UTF-8. The legacy encoding mode (`set_system('filename_encoding', 'locale')`) is not supported for extension packages that use strings with non-ASCII characters.

The structure `Hcpar` enables HALCON to pass a mixed type (`MIXED_PAR`), holding any of the basic types in the union `Hpar`, encoded by the specifier `type`. [Figure 4.11](#) shows the corresponding definitions. Thus, it is possible to pass a native array type or to combine different types within an array of `Hcpar` values. For it, the selector `type` must be set to one of the basic type codes `LONG_PAR`, `DOUBLE_PAR`, `HANDLE_PAR` or `STRING_PAR`.

The Extension Package Interface procedures described in [section 5.5](#) on page 72 are used to access the control parameters of HALCON operators and pass the control data arrays through the interface.

Chapter 5

Handling Iconic Objects and Control Parameters

The HALCON Extension Package Interface provides a large set of procedures and macros for handling control parameters and iconic objects. It supports tasks like:

- Accessing iconic input objects in the HALCON database.
- Accessing single iconic objects within a tuple of objects.
- Accessing specific components (regions, gray value channels) of image objects.
- Accessing XLDs.
- Creating iconic output objects in the HALCON database based on the computed results.
- Reading input control parameters.
- Writing output control parameters.

The routines of the Extension Package Interface described in this and the following chapter especially facilitate the programming of support procedures (that is the access of the HALCON database and all the parameter handling).

In this chapter the “low level” interface routines are introduced. They allow a straightforward access to *all* parameters of an operator – to iconic objects (and their components) and to control parameters. Moreover, some routines for creating iconic objects and writing output iconic parameters and control parameters are introduced.

Based on these low level routines a set of *convenience* routines are presented in [chapter 6](#) on page 87. They are designed to further facilitate the programming of very typical support procedures.

5.1 Basic Access to Iconic Input Objects

This section introduces some basic routines for accessing iconic objects (regions, gray value channels, XLDs), see [figure 5.1](#). They form a basic interface to the HALCON database of iconic objects. [Figure 5.2](#) illustrates how they are used to read image and region data from input iconic parameters.

5.1.1 HGetObj

HGetObj (see [figure 5.1](#)) returns the database key (type: Hkey) of an iconic object corresponding to the input object parameter with the index `par_num` of the HALCON operator.

Note that HGetObj automatically checks the result state of the underlying procedure with the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HGetObj yourself.**



Names

HGetObj, HGetComp, HGetRL, HGetImage, HGetXLD

Synopsis

```
#include "Halcon.h"
```

```
HGetObj(  Hproc_handle  proc_handle,
          int           par_num,
          INT4_8        obj_num,
          Hkey          *obj_key)
```

```
HGetComp( Hproc_handle  proc_handle,
           Hkey          obj_key,
           int           comp,
           Hkey          *comp_key)
```

```
HGetRL(   Hproc_handle  proc_handle,
           Hkey          region_key,
           Hrlregion    *region)
```

```
HGetImage( Hproc_handle  proc_handle,
            Hkey          image_key,
            Himage        *image)
```

```
HGetXLD(  Hproc_handle  proc_handle,
           Hkey          obj_key,
           int           xld_type,
           Hpoly|Hcont  **xld)
```

Figure 5.1: Basic routines for accessing iconic input objects.




Figure 5.2: Direct access to input image objects.

The iconic object can either be a region (iconic object that contains only a region component), an image (iconic object that contains a region component and one or more image channels), or an XLD (iconic object that contains

```

int8_t   inp_pars;
int32_t  num_objs;
int      p,o;
Hkey     key;
...
/* get number of input iconic parameters:          */
/* note: This number is known in general - it is specified by */
/* the operator header in the corresponding DEF file of the */
/* operator                                          */
HReadGV(proc_handle,HGinp_obj,&inp_pars);
for (p=1; p<=inp_pars; p++) {
    /* get number of input iconic objects per input obj. parameter: */
    HReadGVA(proc_handle,HGnum_obj,&num_objs,p);
    for (o=1; o<=num_objs; o++) {
        HGetObj(proc_handle,p,o,&key); /* get key of iconic object */
        /* further processing ... */
    }
}
}

```

Figure 5.3: Example for HGetObj: Database keys of all iconic objects of all input object parameters.

a contour or a polygon).

The parameters of a HALCON operator are numbered consecutively from 1 to n (not from 0 to $n - 1$) for each parameter class (input/output iconic object/control). The parameter `par_num` of HGetObj refers to this index, thus specifying the desired input iconic parameter. All *objects* passed within a single input iconic parameter are numbered from 1 to m , with the first iconic object in the list having the index 1. The parameter `obj_num` of HGetObj denotes the index of a desired iconic object within this list ($1 \leq \text{obj_num} \leq m$).

The total number of input iconic parameters for an operator is specified in the corresponding DEF file¹, but the number of objects *within* an input iconic parameter is dynamic. This value is accessible via the Extension Package Interface routine HReadGVA:

```
HReadGVA(proc_handle,HGnum_obj,&num_objs,p);
```

where `p` denotes the parameter index and `num_objs` is the desired number of iconic objects. As an alternative for reading the number of iconic objects of an input iconic parameter without the routine HReadGVA, you can use the macro HGetObjNum (see section 5.2.5 on page 65).

Note that a loop over all iconic objects passed to an operator within an input iconic object parameter is a very common task. Therefore, HALCON provides a macro for this problem: See HAllObj in section 5.3.1 on page 66.

5.1.2 HGetComp

HGetComp (see figure 5.1 on page 58) returns the database key of an image component (image matrix, i.e., channel: `image_key` or domain, i.e., area of definition: `region_key`) of an image object that is stored under the key `obj_key` in the HALCON database of iconic objects.

Note that HGetComp automatically checks the result state of the underlying procedure with the macro HCkP (see section 5.6.1 on page 83). Thus, **you must not use HCkP on HGetComp yourself**.

All components of an iconic object are consecutively numbered from 0 to n , with 0 denoting the region (domain) and $1 \dots n$ denoting the channels (image matrices). To get a better legibility of program code, the constants REGION (= 0), IMAGE_INDEX (= 1), IMAGE1 (= 1), IMAGE2 (= 2), etc. have been defined globally and may be used as parameter values.

The number of channels per image object `obj_num` of parameter `par_num` is accessible via HNumOfChannels, see figures 5.4 and 5.5:

¹So this number is actually *known* by the programmer. However, using HReadGV it can be read from the operator context as well, see figure 5.3.



```

int    obj_channels;
Hkey   obj_key;
Hkey   region_key;
Hkey   image_key;
...
/* get key of object: */
HGetObj(proc_handle,p,o,&obj_key);
/* get key of region: */
HGetComp(proc_handle,obj_key,REGION,&region_key);
/* get number of channels: */
HCKP(HPNumOfChannels(proc_handle,p,o,&obj_channels));
for (i=1; i<=obj_channels; i++) {
    /* get image matrix key: */
    HGetComp(proc_handle,obj_key,i,&image_key);
    /* ...further processing */
}

```

Figure 5.4: Example for HGetComp: Database keys of all regions and channels within an input image object.

Names

HPNumOfChannels

Synopsis

```

#include "Halcon.h"

Herror HPNumOfChannels( Hproc_handle proc_handle,
                       int           par_num,
                       INT4_8        obj_num,
                       int           *chn_num)

```

Figure 5.5: Auxiliary routine HPNumOfChannels .

```
HPNumOfChannels(proc_handle,par_num,obj_num,&obj_channels)
```

See also HNumOfChannels in [section 5.6.4](#) on page 84 for a convenience version of this routine when dealing with the first input iconic parameter. More examples of how to use HGetComp can be found in [figure 5.6](#) on page 61 and [figure 5.7](#) on page 61.

5.1.3 HGetRL

HGetRL (see [figure 5.1](#) on page 58) reads the runlength encoding of a region (type: Hrlregion, see [section 4.2](#) on page 50) denoted by the database key region_key (type Hkey) from the HALCON database.



Note that HGetRL automatically checks the result state of the underlying procedure with the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HGetRL yourself.**

Since the region data is *copied* to region, it might be overwritten with new values (in contrast to HGetImage and HGetFDRL, cf. [section 5.1.4](#) and [section 5.2.2](#) on page 62). However, this means that enough memory for region must be allocated *before* calling HGetRL, see [section 3.2.1](#) on page 41.

[Figures 5.6](#) and [5.7](#) show example applications of HGetRL.

```

Hrregion  *region;
Hkey      obj_key;
Hkey      region_key;
...
HCkP(HAllocRLTmp(proc_handle,&region));
HGetObj(proc_handle,p,o,&obj_key);
HGetComp(proc_handle,obj_key,REGION,&region_key);
HGetRL(proc_handle,region_key,region);
/* processing (in general this should be done calling an action proc.) */
area = 0;
for (i=0; i<region->num; i++)
    area += region->rl[i].ce - region->rl[i].cb + 1;
HCkP(HFreeRLTmp(proc_handle,region));

```

Figure 5.6: Example for HGetRL: Calculate the area of a region.

5.1.4 HGetImage

HGetImage (see [figure 5.1](#) on page 58) reads the image data (type: Himage, see [section 4.1](#) on page 49) of a specific gray value component (i.e., channel) of an image object referenced by its database key (type Hkey) in the HALCON database.

Note that HGetImage automatically checks the result state of the underlying procedure with the macro HCkP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCkP on HGetImage yourself**.

```

Hkey      obj_key;
Hkey      image_key;
Hkey      region_key;
Himage    image;
Hrregion  *region;
...
HGetComp(proc_handle,obj_key,IMAGE_INDEX,&image_key);
HGetComp(proc_handle,obj_key,REGION,&region_key);
HGetImage(proc_handle,image_key,&image);
HGetRL(proc_handle,region_key,region);
switch (image.kind) {
    case BYTE_IMAGE:
        /* processing (in general this should
        /* be done calling an action procedure) */
        area = sum = 0;
        for (c=0; c<region->num; c++) {
            for (i=CB(region->rl,c,image.width);
                i<=CE(region->rl,c,image.width); i++, area++)
                sum += image.pixel.b[i];
        }
        average = sum / area;
        break;
    default: return(H_ERR_WIT); /* wrong image type */
}

```

Figure 5.7: Example for HGetImage: Average gray value of first channel.

The data structure Himage contains the gray values, the gray value type, and the size of the image matrix. Instead of copying the image matrix, HGetImage only returns a *pointer* to the raw data in `image.pixel`. This is much more efficient, but means that **only read access to the image matrix is recommended** (otherwise you will encounter unpredictable side effects). [Figure 5.7](#) shows an application of HGetImage.



5.1.5 HGetXLD

HGetXLD (see [figure 5.1](#) on page 58) is used to access XLD objects in the HALCON database of iconic objects. The object of interest is specified by the database key `obj_key`. The parameter `xld_type` allows to specify the kind of XLD data to be accessed: It has to be set to `XLD_CONTOUR_ID` in case of a contour and to `XLD_POLYGON_ID` in case of a polygon. Corresponding to the selected type, HGetXLD expects a pointer to `Hcont` or a pointer to `Hpoly` in the parameter `xld`. In both cases *not* the underlying data within the structures `Hcont` or `Hpoly` but only the *pointers* to the data are copied from the database. Thus, **please avoid any write access to this data**. Otherwise you will encounter unpredictable side effects (changing other iconic objects). [Figure 5.8](#) shows a simple example for how to use HGetXLD.



Note that HGetXLD automatically checks the result state of the underlying procedure with the macro `HCKP` (see [section 5.6.1](#) on page 83). Thus, **you must not use `HCKP` on HGetXLD yourself**.



```
Hkey      obj_key;
Hcpar     num_points;
Hcont     *cont;

HGetObject(proc_handle, par_num, obj_num, &obj_key);
HGetXLD(proc_handle, obj_key, XLD_CONTOUR_ID, (void*)&cont);

/* processing (in general this should be done calling an action proc.) */
num_points.type = LONG_PAR;
num_points.par.1 = cont->num;
HPutCPar(proc_handle, 1, &num_points, 1);
```

Figure 5.8: Example for HGetXLD: Return the number of points of the contour with the index `obj_num` within input iconic parameter `par_num`.

5.2 Additional Routines for Accessing Input Image Objects

This section introduces some routines that ease the programming of supply procedures in many applications, see [figure 5.9](#). Basically they are combinations of the routines described in the previous section. These additional routines only require the database keys of the input iconic objects that can be extracted by using the routines `HGetObject` (see [section 5.1.1](#) on page 57) or `HALlObj` (see [section 5.3.1](#) on page 66). For `HGetURL`, even this step can be omitted.

5.2.1 HGetDRL

HGetDRL (see [figure 5.9](#)) combines `HGetComp` ([section 5.1.2](#) on page 59) and `HGetRL` ([section 5.1.3](#) on page 60). It reads the runlength encoding of a region (type: `Hrlregion`, see [section 4.2](#) on page 50) specified by the database key `obj_key` of an image object. The region data is *copied* to `region`, which must have been allocated before with a suitable size (e.g., by using `HALlocRLTmp`, see [section 3.2.1](#) on page 41). Therefore, this region data can be overwritten without side effects. On the other hand, the memory must be deallocated at the end of the supply procedure (e.g., by using `HFreeRLTmp`). [Figure 5.10](#) shows an example application of HGetDRL.



Note that HGetDRL automatically checks the result state of the underlying procedure with the macro `HCKP` (see [section 5.6.1](#) on page 83). Thus, **you must not use `HCKP` on HGetDRL yourself**.

5.2.2 HGetFDRL

In contrast to HGetDRL, only a pointer to the region data is returned by HGetFDRL (see [figure 5.9](#)). So there is no need to allocate memory for the data. On the other hand, only read access to the data is allowed. An example application of HGetFDRL can be seen in [figure 5.11](#).



Note that HGetFDRL automatically checks the result state of the underlying procedure with the macro `HCKP` (see [section 5.6.1](#) on page 83). Thus, **you must not use `HCKP` on HGetFDRL yourself**.

Names

HGetDRL, HGetFDRL, HGetURL, HGetDImage, HGetObjNum

Synopsis

```
#include "Halcon.h"

HGetDRL(  Hproc_handle  proc_handle,
          Hkey          obj_key,
          Hrlregion    *region)

HGetFDRL( Hproc_handle  proc_handle,
          Hkey          obj_key,
          Hrlregion    **region)

HGetURL(  Hproc_handle  proc_handle,
          int           par_num,
          Hrlregion    *region)

HGetDImage(Hproc_handle  proc_handle,
           Hkey          obj_key,
           int           channel,
           Himage       *image)

HGetObjNum(Hproc_handle  proc_handle,
           int           par_num,
           INT4_8       *num)
```

Figure 5.9: Additional routines for accessing input image objects.

```
Hrlregion *region;
Hkey      obj_key;
...
HCKP(HALlocRLTmp(proc_handle,&region));
HGetObj(proc_handle,par_num,obj_num,&obj_key);
HGetDRL(proc_handle,obj_key,region);
/* processing (in general this should be done calling an action proc.) */
area = 0;
for (i=0; i<region->num; i++)
    area += region->rl[i].ce - region->rl[i].cb + 1;
HCKP(HFreeRLTmp(proc_handle,region));
```

Figure 5.10: Application of HGetDRL.

5.2.3 HGetURL

HGetURL (see [figure 5.9](#)) reads all regions passed in the input iconic parameter with the index `par_num`, computes the union of all these regions, and returns the resulting region in `region`. The `Hrlregion` data referenced by

```
Hkey      obj_key;
Hrlregion *region;
...
HGetFDRL(proc_handle,obj_key,&region);
/* processing (in general this should be done calling an action proc.) */
area = 0;
for (i=0; i<region->num; i++)
    area += region->rl[i].ce - region->rl[i].cb + 1;
```

Figure 5.11: Application of HGetFDRL.

region must have been allocated before with a suitable size (e.g., by using `HAllocRLTmp`, see [section 3.2.1](#) on page 41, which can be increased e.g., by using `HIncrRL`, see [section 5.6.5](#) on page 84). Therefore, this region data can be overwritten without side effects. On the other hand, the memory must be deallocated at the end of the supply procedure (e.g., by using `HFreeRLTmp`). [Figure 5.12](#) shows an application of `HGetURL`. Note that the area calculated in the example may differ from the sum of the areas of all single regions, because the single regions may overlap.



Note that `HGetURL` automatically checks the result state of the underlying procedure with the macro `HCKP` (see [section 5.6.1](#) on page 83). Thus, **you must not use `HCKP` on `HGetURL` yourself.**

If you do not want to have the result state checked with `HCKP`, use `HPGetURL` instead. `HPGetURL` and `HGetURL` only differ regarding `HCKP`.

```
Hrlregion *region;
...
HCKP(HAllocRLTmp(proc_handle,&region));
HGetURL(proc_handle,par_num,region);
/* processing (in general this should be done calling an action proc.) */
area = 0;
for (i=0; i<region->num; i++)
    area += region->rl[i].ce - region->rl[i].cb + 1;
HCKP(HFreeRLTmp(proc_handle,region));
```

Figure 5.12: Application of `HGetURL`.

5.2.4 HGetDImage

`HGetDImage` (see [figure 5.9](#) on page 63) combines `HGetComp` ([section 5.1.2](#) on page 59) and `HGetImage` ([section 5.1.4](#) on page 61). It reads the data of the gray value component channel of the image object specified by the database key `obj_key` and returns it in the `Himage` structure (`image`).



Note that `HGetDImage` automatically checks the result state of the underlying procedure with the macro `HCKP` (see [section 5.6.1](#) on page 83). Thus, **you must not use `HCKP` on `HGetDImage` yourself.**

```
Himage image;
Hcpar row,col,gray;
...
HGetSPar(proc_handle,1,LONG_PAR,&row,1); /* row */
HGetSPar(proc_handle,2,LONG_PAR,&col,1); /* column */
coord = HLinCoor(row.par.l,col.par.l,image.width);
HGetDImage(proc_handle,obj_key,IMAGE_INDEX,&image);
/* processing (in general this should be done calling an action proc.) */
switch (image.kind) {
case BYTE_IMAGE:
    gray.par.l = image.pixel.b[coord];
    gray.type = LONG_PAR;
    break;
case FLOAT_IMAGE:
    gray.par.d = image.pixel.f[coord];
    gray.type = DOUBLE_PAR;
    break;
default:
    return(H_ERR_WIT); /* wrong image type */
}
HPutCPar(proc_handle,1,&gray,1);
```

Figure 5.13: Application of `HGetDImage`: Return the gray value at position (row,col) in the first channel of the input iconic object `obj_key`.

For the sake of efficiency, only a *pointer* to the image matrix is copied to `image`, instead of copying the data itself. So, only read access to the image data is recommended in order to avoid unpredictable side effects. [Figure 5.13](#) shows an application of `HGetDImage`.

5.2.5 HGetObjNum

HGetObjNum (see [figure 5.9](#) on page 63) returns the number of iconic objects which are stored in the input iconic parameter denoted by its index `par_num` (from 1 to n). It is an alternative to the usage of `HReadGVA` (compare [page 59](#)). By using `HGetObjNum`, the example of [figure 5.3](#) on page 59 looks as follows (see [figure 5.14](#)).

Note that `HGetObjNum` automatically checks the result state of the underlying procedure with the macro `HCKP` (see [section 5.6.1](#) on page 83). Thus, **you must not use `HCKP` on `HGetObjNum` yourself.**



```
int    inp_pars;
INT4_8 num_objs;
Hkey   key;
int    p,o;
...
/* get number of input iconic parameters:          */
/* note: This number is known in general - it is specified by */
/* the operator header in the corresponding DEF file of the */
/* operator                                          */
HReadGV(proc_handle,HGinp_obj,&inp_pars);
for (p=1; p<=inp_pars; p++) {
    /* get number of iconic objects per input iconic parameter: */
    HGetObjNum(proc_handle,p,&num_objs);
    for (o=1; o<=num_objs; o++) {
        HGetObj(proc_handle,p,o,&key); /* get key of iconic object */
        /* further processing ... */
    }
}
}
```

Figure 5.14: Application of `HGetObjNum`: Access the number of iconic objects of an input iconic parameter.

5.3 Loop Macros for Accessing Single Input Objects

This section describes two macros that ease the access of *all* iconic objects and image components within an input iconic parameter, see [figure 5.15](#). Please see also the additional loop macros in [section 6.1](#) on page 87 that further facilitate the programming of typical supply procedure.

Names

`HA11Obj`, `HA11Comp`

Synopsis

```
#include "Halcon.h"
```

```
HA11Obj( Hproc_handle  proc_handle,
        int            par_num,
        Hkey           &obj_key,
        INT4_8         &index)
```

```
HA11Comp(Hproc_handle  proc_handle,
        Hkey           obj_key,
        Hkey           &image_in_key,
        Himage         &image_in,
        INT4_8         &index)
```

Figure 5.15: Basic loop macros to access iconic objects. “&” denotes output parameters of the macros. This is only a special notation to make clear that these parameters are *changed* by the macros. So do *not* pass pointers to variables but the variables itself to the macro.

5.3.1 HA11Obj

HA11Obj (see [figure 5.15](#)) performs a loop over all iconic objects of a specified input iconic parameter and returns their database key.

```
Hkey      obj_key;
Hrregion  *region;
Himage    image;
INT4_8    index;
...
HA11Obj(proc_handle,1,obj_key,index) {
    HGetFDRL(proc_handle,obj_key,&region);
    HGetDImage(proc_handle,obj_key,IMAGE_INDEX,&image);
}
```

Figure 5.16: Application of HA11Obj: Access the domain (area of definition) and the first gray value channel of all iconic objects of the first input iconic parameter.

Within the loop, all iconic objects contained in the input iconic parameter with the index² `par_num` are accessed one by one. `index` is set to the index of the current iconic object to be processed and `obj_key` is set to the corresponding database key. Thus, using HA11Obj is equivalent to programming an explicit loop over all iconic objects contained in a parameter and determining the database keys via HGetObj, see also [figure 5.3](#) on page 59. [Figure 5.16](#) shows an application of HA11Obj.

5.3.2 HA11Comp

HA11Comp performs a loop over all gray value channels (components) of the image object denoted by the database key `obj_key`. Within the loop, `image_in_key` is set to the database key of the current image object and the corresponding image data is delivered in `image_in`. Using HA11Comp is equivalent to programming an explicit loop over all channels of an image object using HGetDImage. This also implies that the raw image data, i.e., the image matrix itself, is *not* copied. Instead, only a pointer to this data is inserted in `image_in`. So please restrict yourself to *reading* this data. **Any write access to the image matrix will cause unpredictable side effects.**



Note that HA11Comp does *not* check, whether the image object contains at least one channel. Note further, that **any region processing should be performed outside the loop** (otherwise you will process the same region again and again for each channel).

```
Hkey      obj_in;
Hkey      obj_out;
Hkey      image_in_key;
INT4_8    comp_index;
Himage    image_in,image_out;
...
HA11Obj(proc_handle,1,obj_in,j) {
    HCrObj(proc_handle,1,&obj_out);
    HA11Comp(proc_handle,obj_in,image_in_key,image_in,comp_index) {
        HCKP(HCrImage(proc_handle,image_in_key,1,BYTE_IMAGE,
            image_in.width,image_in.height,
            &im_out_key,&image_out));
        HCKP(IPBRot90(image_in.pixel.b,image_in.width,region_in,
            image_out.pixel.b,width,height));
        HDefObj(proc_handle,obj_out,im_out_key,comp_index);
    }
}
```

Figure 5.17: Application of HA11Comp: Rotate all channels of all image objects of the first input iconic parameter.

[Figure 5.17](#) shows an example of how to use HA11Comp. Within the HA11Obj loop for each input image object, an output image object is created and added to the iconic object list of the first output iconic parameter (HCrObj, see

²So in contrast to the routines described in [section 6.1](#) on page 87, HA11Obj allows to specify the desired parameter by its index.

section 5.4.1). After that, a loop over all gray value channels of the current image object is performed (HAL1Comp). Within this loop, for every gray value channel a new image matrix is created (HCrImage, see section 5.4.7 on page 70) and filled with the rotated input matrix (IPBRot90). Finally, this matrix is installed as a new gray value channel of the output image object (HDefObj, see section 5.4.5 on page 69). The corresponding region transformation (rotating the region and defining the rotated region as new domain, i.e., area of definition, of the output image object via HDefObj) is omitted in this example.

5.4 Creating Objects and Writing Output Object Parameters

This section describes routines for creating new iconic objects in the HALCON database of iconic objects and for writing output iconic parameters of a HALCON operator, see figure 5.18. Note that regions, gray value channels, and XLDs are all stored as individual iconic objects within the database. Thus, for example different image objects can *share* the same gray value channels (image matrices) or domains (areas of definition). Therefore, in order to return iconic objects as the result of a HALCON operator you have to

- store the computed regions, channels, and XLDs in the HALCON database of iconic objects,
- combine regions and channels to image objects,
- and add the appropriate iconic objects to the corresponding output iconic parameters.

Names

HCrObj, HCopyObj, HPutDRL, HPutImage

Synopsis

```
#include "Halcon.h"
```

```
HCrObj(      Hproc_handle  proc_handle,
             int           par_num,
             Hkey         *obj_key)
```

```
HCopyObj(   Hproc_handle  proc_handle,
             Hkey         obj_key,
             int         par_num,
             Hkey         *obj_key)
```

```
HPutDRL(    Hproc_handle  proc_handle,
             Hkey         obj_key,
             Hrlregion   *region,
             Hkey         *rl_key)
```

```
HPutImage(  Hproc_handle  proc_handle,
             Himage      *image,
             bool        copy,
             Hkey         *obj_key)
```

Figure 5.18: Basic routines for creating new iconic objects and writing output iconic parameters (to be continued).

5.4.1 HCrObj

HCrObj (see figure 5.18) creates a new image object in the HALCON database of iconic objects and adds it to the list of iconic objects in the output iconic parameter with the index `par_num`. Note that more than one image object can be returned in the same output parameter by iterating calls of HCrObj using the same `par_num`: Each call appends the database key of the new iconic object at the end of the iconic object list for the parameter.

The new image object contains the following default image components:

Names

HDefObj, HPutDImage, HCrImage, HCrXLD

Synopsis

```
#include "Halcon.h"

HDefObj(      Hproc_handle  proc_handle,
              Hkey          obj_key,
              Hkey          comp_key,
              int           comp)

HPutDImage(   Hproc_handle  proc_handle,
              Hkey          obj_key,
              int           comp,
              Himage        *image,
              bool          copy,
              Hkey          *image_key)

Herror HCrImage( Hproc_handle  proc_handle,
                 Hkey          image_key_in,
                 int           index,
                 int           type,
                 HIMGDIM      width,height,
                 Hkey          *image_key_out,
                 Himage        *image_out)

HCrXLD(       Hproc_handle  proc_handle,
              int           par_num,
              XLD           *xld,
              int           xld_type,
              Hkey          *used_xlds,
              int           num_used_xlds,
              DBFreeProc    free_proc,
              Hkey          *obj_key)
```

Figure 5.19: Basic routines for creating new iconic objects and writing output iconic parameters (continued).

- The region component specifying the area of definition, i.e., the domain of the image, is set to the empty region. This component can be changed using HPutDRL (see [section 5.4.3](#) on page 69) or HPutRect (see [section 6.2.2](#) on page 94).
- All channels are marked as undefined, i.e., the new image object contains no gray value components. Channels can be added to the iconic object using HPutImage (see [section 5.4.4](#)) and HDefObj (see [section 5.4.5](#)) or HPutDImage (see [section 5.4.6](#) on page 70).

Figure 5.17 on page 66 and figure 5.21 on page 70 show examples how to use HCrObj.

Note that HCrObj automatically checks the result state of the underlying procedure with the macro HCkP, (see [section 5.6.1](#) on page 83). Thus, **you must not use HCkP on HCrObj yourself.**

5.4.2 HCopyObj

HCopyObj (see [figure 5.18](#) on page 67) creates a new *iconic* object (image, region, or XLD) that contains the same components as an already existing iconic object specified by its database key obj_key. The new iconic object is stored in the HALCON database of iconic objects and appended to the list of iconic objects in the output iconic parameter with the index par_num. The database key of the new image object is returned in obj_key.

Note that HCopyObj automatically checks the result state of the underlying procedure with the macro HCkP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCkP on HCopyObj yourself.**

```

Hkey      obj_key_in,obj_key_out,reg_key_out;
Hrregion  *region_in;
Hrregion  *region_out;
INT4_8    num_objs;
...
par_in = 1; /* index of input parameter */
par_out = 1; /* index of output parameter */
HReadGVA(proc_handle,HGnum_obj,&num_objs,par_in);
for (o=1; o<=num_objs; o++) {
    HGetObj(proc_handle,par_in,o,&obj_key_in);
    HGetFDRL(proc_handle,obj_key_in,&region_in);
    /* compute some region transformation ... */
    transform(region_in,region_out);
    HCopyObj(proc_handle,obj_key_in,par_out,&obj_key_out);
    HPutDRL(proc_handle,obj_key_out,region_out,&reg_key_out);
}

```

Figure 5.20: Create an image object with HCopyObj and insert a region component.

Similar to HCrObj, the components of a new *image* object can be reassigned using HDefObj etc. HCopyObj is especially useful, when output iconic objects hardly differ from the corresponding input objects.

5.4.3 HPutDRL

HPutDRL (see [figure 5.18](#) on page 67) stores region data encoded in the Hrregion structure region in the HALCON database of iconic objects and returns the database key of the new iconic object. Note that HPutDRL actually *copies* the data itself, not only a pointer to the data. In addition to that, the region object is assigned to the image object specified by the database key obj_key as the region component. The latter might have been created before by using HCrObj or HCopyObj, see [figures 5.20](#) and [5.21](#).

Note that HPutDRL automatically checks the result state of the underlying procedure with the macro HCkP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCkP on HPutDRL** yourself.

5.4.4 HPutImage

HPutImage (see [figure 5.19](#) on page 68) stores the gray value channel (image matrix) image in the database of iconic objects and returns the corresponding database key in the parameter obj_key. This key can be used to insert the gray value channel (now encapsulated in a database object) as a component of an arbitrary number of image objects (see HDefObj in [section 5.4.5](#)). The parameter copy (false or true) specifies, whether the pixel data is *copied* to the HALCON database³ or only the address of the data is passed to the database object. [Figure 5.21](#) shows a typical example for how to use HPutImage.

Note that HPutImage automatically checks the result state of the underlying procedure with the macro HCkP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCkP on HPutImage** yourself.

5.4.5 HDefObj

HDefObj (see [figure 5.19](#) on page 68) reassigns the component comp (0...n) of an image object given by its database key comp_key. A typical application of this routine is shown in [figure 5.21](#): Image data is stored in a database object using HPutImage. Furthermore, a new image object is created by HCrObj. This new object does not contain any gray value channels, see [section 5.4.1](#) on page 67. Using HDefObj, the previously stored image data is assigned as default gray value component 1 (IMAGE_INDEX) of the new image object.

Note that HDefObj automatically checks the result state of the underlying procedure with the macro HCkP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCkP on HDefObj** yourself.

³This is necessary if the original data is stored in temporary memory or if the data will be modified later on.

```

Himage    image;
Hrregion *region;
Hkey      image_key,obj_key;
...
/* processed image data:  image */
/* processed region data: region */
par_num = 1;
HPutImage(proc_handle,&image,true,&image_key);
HCrObj(proc_handle,par_num,&obj_key);
HDefObj(proc_handle,obj_key,image_key,IMAGE_INDEX);
HPutDRL(proc_handle,obj_key,region,&region_key);

```

Figure 5.21: Creating a new image object using basic Extension Package Interface routines.

5.4.6 HPutDImage

HPutDImage (see [figure 5.19](#) on page 68) combines HPutImage and HDefObj. It stores the gray value channel (image matrix) image in the HALCON database of iconic objects and returns the corresponding database key in image_key. The parameter copy (false or true) is used as in HPutImage and specifies, whether the pixel data is *copied*⁴ or only a pointer to the data is passed to the database. Moreover, the gray value channel is inserted into the image object obj_key as component comp (1 . . . n). [Figure 5.22](#) shows a typical application of this routine.



Note that HPutDImage automatically checks the result state of the underlying procedure with the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HPutDImage yourself.**

```

Hkey      obj_key,k;
Himage    image;
Hrregion *region;
...
/* image:  processed gray value data */
/* region: region data                */
HCrObj(proc_handle,par_num,&obj_key);
HPutDImage(proc_handle,obj_key,IMAGE_INDEX,&image,false,&k);
HPutDRL(proc_handle,obj_key,region,&k);

```

Figure 5.22: Creating a new image object using HPutDImage and HPutDRL.

5.4.7 HCrImage

HCrImage (see [figure 5.19](#) on page 68) is used for creating output images especially in the context of filter⁵ operations. As you know, HALCON image objects can share the underlying image matrices (gray value channels). Thus, input image objects of a filter operation might only differ in their domain (i.e., in their region component), but *not* in their gray values. Such objects have different database keys and different regions, but contain references to the same gray value channels. Obviously, it is very desirable to propagate this relation to the resulting output image objects as well.

HCrImage allocates memory for the image matrix within the Himage structure image_out (similar to HNewImage in [section 3.2.2](#) on page 43). The parameters type (BYTE_IMAGE, LONG_IMAGE, FLOAT_IMAGE, etc.; see [figure 4.2](#) on page 50, width and height allow to specify the pixel type and the size of the new matrix. Note that new matrices are by default initialized with 0. However, this can be suppressed from outside or inside of the operator, see the discussion of HNewImage in [section 3.2.2](#) on page 43 for details.

Furthermore, HCrImage creates a new database object encapsulating this image data and returns the corresponding database key in image_key_out (similar to HPutImage in [section 5.4.4](#) on page 69).

Finally, HCrImage establishes a link between the original input image data (referenced by the database key image_key_in) and this new iconic object to avoid the allocation of multiple output matrices per input matrix. HCrImage checks, whether there already exists an output matrix with the specified index index (see below)

⁴This is necessary, if the pixel data was stored in temporary memory or if it will be modified later on.

⁵This is due to the fact, that filtering only modifies the gray values but not the regions of image objects.

```

Hkey      obj_key,image_key_in,image_key_out,key_out;
Hrregion  *region;
Himage    image_in,image_out;

...
HGetSPar(proc_handle,1,LONG_PAR,&Rows,1); /* height: filter mask */
HGetSPar(proc_handle,2,LONG_PAR,&Cols,1); /* width: filter mask */

HAllObj(proc_handle,1,obj_key,i) {          /* all input images */
  HGetFDRL(proc_handle,obj_key,&region); /* get region data */
  HGetComp(proc_handle,obj_key,IMAGE1,&image_key_in);
  if (image_key_in == UNDEFINED)
    return(H_ERR_UNDI);                    /* 'undefined image' */
  HGetImage(proc_handle,image_key_in,&image_in); /*get image data*/
  HCkP(HCrImage(proc_handle,image_key_in,1,image_in.kind,
                image_in.width,image_in.height,
                &image_key_out,&image_out));

  HCkP(IPFilterOperation(&image_in,region,Rows,Cols,&image_out));

  HCopyObj(proc_handle,obj_key,1,&key_out); /* create result obj.*/
  HDefObj(proc_handle,key_out,image_key_out,IMAGE1);
  /* insert the result image in output object */
}

```

Figure 5.23: A typical example for using HCrImage: Providing an empty image matrix for a filter operation.

for a given input image `image_key_in`. If there is any, only a reference to it is returned in `image_out` and `image_key_out` instead of creating a new matrix. Without this mechanism, a new matrix would be created again and again within the loop over all input iconic objects (HAllObj).

The parameter `index` is only of importance, if *more* than one output matrix per input matrix is needed: This is necessary for example, if an edge filter is performed in x- and y-direction *independently*. In this case, HCrImage must be called several times for every input component – one time for each output matrix to be created. Assign increasing indices (1, 2, 3, ...) to the parameter `index` to indicate a new output matrix. If there is only one matrix to create for the output image, set `index` to 1.

Figure 5.23 shows an exemplary application of HCrImage.

Note that HCrImage is no macro, i.e., it does not check the result state of the underlying procedure using HCkP (see section 5.6.1 on page 83). Thus, **you must call HCkP on HCrImage yourself** as shown in the example.

5.4.8 HCrXLD

HCrXLD (see figure 5.19 on page 68) is used for creating XLD objects in the HALCON database of iconic objects. The parameter `xld_type` allows to specify the kind of XLD to be created: It has to be set to `XLD_CONTOUR_ID` in case of a contour and to `XLD_POLYGON_ID` in case of a polygon. Corresponding to the selected type, HCrXLD expects a pointer to `Hcont` or a pointer to `Hpoly` in the parameter `xld`. In both cases, *not* the underlying XLD data but only the *pointers* to the data are copied to the database. Thus, **you must not deallocate or overwrite the XLD structures** after calling HCrXLD.

Note that HCrXLD automatically checks the result state of the underlying procedure with the macro HCkP (see section 5.6.1 on page 83). Thus, **you must not use HCkP on HCrXLD yourself**.

HCrXLD expects an appropriate deallocation routine for the XLD data in the parameter `free_proc`. For XLD contours, please use

```
(DBFreeProc) HXLDFreeContour
```

For XLD polygons allocated based on HAlloc use



```

Hcpar    rows[99], cols[99];
INT4_8   i,num_points;
Hkey     key_out;
Hcont    *cont;

...
HGetCPar(proc_handle,1,DOUBLE_PAR,rows,1,99,&num_points);
HGetCPar(proc_handle,2,DOUBLE_PAR,cols,1,99,&num_points);

/* create a contour (in general, this should be done */
/* calling an appropriate action procedure)          */
HCkP(HALlocXLDCont(proc_handle,&cont,num_points));
for (i=0; i < num_points; i++ {
    cont->row[i] = rows[i].par.d;
    cont->col[i] = cols[i].par.d;
}
cont->num = num_points;
HCrXLD(proc_id,1,cont,XLD_CONTOUR_ID,NULL,0,
        (DBFreeProc)HXLDFreeContour,&key_out);

```

Figure 5.24: A typical example for using HCrXLD: Create an XLD contour from a list of points.

```
(DBFreeProc) HXLDFreePolygon
```

Finally, HCrXLD not only creates a new database object, but also appends this object to the output iconic parameter with index `par_num`. [Figure 5.24](#) shows a typical application of HCrXLD.

5.5 Reading and Writing Control Parameters

This section describes routines for reading and writing in-/output control parameters, see [figure 5.25](#), [figure 5.29](#), [figure 5.30](#), and [figure 5.35](#). Interchanging control data with the host language is done via arrays of the data type `INT4_8` for `LONG_PAR`, `double` for `DOUBLE_PAR`, `Hphandle` for `HANDLE_PAR`, `char*` for `STRING_PAR`, or `Hcpar` for `MIXED_PAR` array types (see [section 4.4](#) on page 55).

Control parameters can be passed through the HALCON interface in two different ways: by reference or by value. The former is more efficient but does not allow to modify the values. It is supported by the routines `HGetPElemL`, `HGetPElemD`, `HGetPElemS`, and `HGetPPar` for reading, depending on the expected type of the input array. `HGetPElem` provides a general, type independent read access. In case of writing output control parameters, `HPutPPar` and `HPutPElem` are provided. In contrast, the routines `HGetElemL`, `HGetElemD`, `HGetElemS`, `HGetCElemH1`, `HGetCElemH`, `HGetCElemHN`, and `HGetCPar` return a copy of the input array, whereas `HPutElem`, `HPutElemH`, and `HPutCPar` copy an array to an output control parameter.

5.5.1 HGetPElemL, HGetPElemD, HGetPElemS

`HGetPElemL`, `HGetPElemD`, and `HGetPElemS` (see [figure 5.25](#)) return a reference in `elem` to the value array of the input control parameter at the position `par` (1 . . . *n*). According to the expected type of the array, `HGetPElemL` is used to get `LONG_PAR` arrays, `HGetPElemD` for `DOUBLE_PAR`, and `HGetPElemS` for `STRING_PAR` arrays. The behavior of the routines in case of passing array types different to the expected can be specified by the `convert` parameter. Following values are supported:

`CONV_NONE` supports no conversion and accepts only the requested element type. Otherwise, the error 'wrong type of input parameter x' (`H_ERR_WIPTx`) will be returned.

`CONV_CAST` provides conversion of `LONG_PAR` and `DOUBLE_PAR` values to the requested type by a cast. In case of conversion, the array is copied to an ad hoc allocated memory buffer. This buffer is freed automatically when the operator returns. `LONG_PAR` and `DOUBLE_PAR` value types can not be casted to type `STRING_PAR` and vice versa. In this case, error 'wrong type of input parameter x' (`H_ERR_WIPTx`) will be returned.

Names

HGetPElemL, HGetPElemD, HGetPElemS, HGetPPar, HGetPElem

Conversion Flags

```

CONV_NONE /* no conversion; do only consider original element types */
CONV_CAST /* <INT4_8>=(INT4_8)<double>; <double>=(double)<INT4_8> */
CONV_IDNT /* convert double to INT4_8, if double has no fraction */
CONV_RND /* <INT4_8>=(INT4_8)(<double>+0.5) */

```

Synopsis

```

#include "Halcon.h"

HGetPElemL(      Hproc_handle      proc_handle,
                 int                par,
                 int                convert,
                 INT4_8 const*restrict *elem,
                 INT4_8             *num)

HGetPElemD(      Hproc_handle      proc_handle,
                 int                par,
                 int                convert,
                 double const*restrict *elem,
                 INT4_8             *num)

HGetPElemS(      Hproc_handle      proc_handle,
                 int                par,
                 int                convert,
                 char const* const*restrict *elem,
                 INT4_8             *num)

HGetPPar(        Hproc_handle      proc_handle,
                 int                par,
                 Hcpar* restrict    *val,
                 INT4_8             *num)

HGetPElem(       Hproc_handle      proc_handle,
                 int                par,
                 void const*restrict *elem,
                 INT4_8             *num,
                 int                *type)

```

Figure 5.25: Routines for reading control input parameters by reference.

CONV_IDNT converts DOUBLE_PAR values of a DOUBLE_PAR or MIXED_PAR array to type LONG_PAR when passed to HGetPElemL. This conversion is performed only if all double values of the input array have no fraction, i.e., the cast is reversible. When passed to HGetPElemD, values of type LONG_PAR are casted to type DOUBLE_PAR. Any other conversion is not supported and in this case the error 'wrong type of input parameter x' (H_ERR_WIPTx) is returned. In case of conversion, the array is copied to an ad hoc allocated memory buffer. This buffer is freed automatically when the operator returns.

CONV_RND provides conversion by rounding when DOUBLE_PAR values have to be converted to LONG_PAR type (HGetPElemD). LONG_PAR values are casted to DOUBLE_PAR if passed to HGetPElemD. Otherwise, the error 'wrong type of input parameter x' (H_ERR_WIPTx) will be returned. In case of conversion, the array is copied to an ad hoc allocated memory buffer. This buffer is freed automatically when the operator returns.

Any conversion of input array types will be paid for by performance and memory consumption. Refer to HGetPElem (see [section 5.5.3](#)) if efficient support of different array types is important. The current number of parameter values is returned in num.



Note that HGetPElemL, HGetPElemD, and HGetPElemS automatically check the result state of the underlying procedure similarly to the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HGetPElemL, HGetPElemD, or HGetPElemS yourself.**

[Figure 5.26](#) shows the usage of HGetPElemL and HGetPElemS together with HGetPPar (compare [section 5.5.2](#)).

5.5.2 HGetPPar

HGetPPar (see [figure 5.25](#) on page 73) returns the reference to a MIXED_PAR array of Hcpar structures, which contain the parameter values of the input control parameter at the position par (1...n). Contrary to HGetCPar (see [section 5.5.7](#) on page 76), HGetPPar is much more efficient in terms of memory overhead, because it just returns pointers to the values instead of copying them. On the other hand, the parameter values may only be read and must not be modified. Note that for every parameter value, its type (LONG_PAR, DOUBLE_PAR, STRING_PAR) is also stored within the Hcpar structure. Therefore, the same control parameter may contain values of different control data types. In case the input array is of different type to MIXED_PAR, the array is copied and converted to an ad hoc allocated memory buffer of Hcpar structures. This buffer is freed automatically when the operator returns. The current number of parameter values is returned in num.



Note that HGetPPar automatically checks the result state of the underlying procedure similarly to the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HGetPPar yourself.**

[Figure 5.26](#) shows the usage of HGetPPar together with HGetPElemL and HGetPElemS (compare [section 5.5.1](#) on page 72).

```

INT4_8 const    *ctrl1; /* LONG_PAR array                */
char const*const *ctrl2; /* STRING_PAR array                */
Hcpar           *ctrl3; /* MIXED_PAR array of Hcpar structures */
INT4_8         num;    /* length of an input array        */

/* Read all values of parameter number 1. Say, we expect a
/* LONG_PAR array but also tolerate double values.
HGetPElemL(proc_handle,1,CONV_CAST,&ctrl1,&num);
/* now ctrl1[0] == 5; ctrl1[1] == 6;
/* Read a string in parameter number 2. Say, we expect a
/* STRING_PAR array.
HGetPElemS(proc_handle,2,CONV_NONE,&ctrl2,&num);
/* now ctrl2[0] == "Text"
/* Read a tuple of float values in parameter number 3.
/* At this parameter we handle any value type
HGetPPar(proc_handle,3,&ctrl_val3,&num);
/* now ctrl3[0].type == DOUBLE_PAR, ctrl3[0].par.d == 1.7
/* ctrl3[1].type == LONG_PAR, ctrl3[1].par.l == 4
/* ctrl3[2].type == STRING_PAR, ctrl3[2].par.s == "ctrl"
...

```

Figure 5.26: Read the control parameter values of the operator call `demo([5,6.8], 'Text', [1.7,4, 'ctrl'])` using HGetPElemL, HGetPElemS, and HGetPPar.

5.5.3 HGetPElem

A general access on input control parameter without any implicate conversion is provided by the routine HGetPElem (see [figure 5.25](#)). HGetPElem returns in elem a reference to the input array of arbitrary type of the input control parameter with the index par (1...n). The length of the array is returned in num. type holds the array type of the returned array and can take the values LONG_PAR, DOUBLE_PAR, STRING_PAR, and MIXED_PAR, coding arrays of type INT4_8, double, char*, and Hcpar, respectively.

[Figure 5.27](#) shows the usage of HGetPElem.

```

const void *restrict ctrl1;
INT4_8      n1;
int         t1;

/* Read all values of parameter number 1 */
HGetPElem(proc_handle, 1, &e1, &n1, &t1);
switch( t1)
{
case LONG_PAR:
{
    INT4_8 const *l = (INT4_8 const *)e1;
    ...
    break;
}
case DOUBLE_PAR:
{
    double const *d = (double const *)e1;
    ...
    break;
}
case STRING_PAR:
{
    char const *const *s = (char const *const *)e1;
    ...
    break;
}
case MIXED_PAR:
{
    Hcpar const *cpar = (Hcpar const *)e1;
    ...
    break;
}
default:
    return H_ERR_WIPT1;
}

...

```

Figure 5.27: Read the control parameter values of the first control parameter of an operator using HGetPElem.

5.5.4 HGetCElemH1, HGetCElemH, HGetCElemHN

HGetCElemH1 retrieves a single handle from an input parameter. HGetCElemH retrieves all handles from an input parameter. HGetCElemHN retrieves a given number N of handles from an input parameter. The returned array contains pointers to the data stored in the handles. It is freed automatically when the operator finishes.

5.5.5 HGetElemL, HGetElemD, HGetElemS

HGetElemL, HGetElemD, and HGetElemS (see [figure 5.29](#)) return a copy of the input control parameter array with the index par (1 . . . n). According to the expected type of the array, HGetElemL is used to get LONG_PAR arrays, HGetElemD for DOUBLE_PAR, and HGetElemS for STRING_PAR arrays. In contrast to HGetPElemL, HGetPElemD, and HGetPElemS, the input arrays will be allocated and the values copied in any case. Therefore, the resulting array can be modified with the drawback of memory overhead and loss of performance. The kind of memory allocation (compare [section 3.2](#) on page 41) can be specified by the parameter memtype. It supports the values HMEMglobal, HMEMlocal, and HMEMtemp, specifying the allocation function HALloc, HALlocLocal, or HALlocTmp that is used internally. The specified function is used by the routines to allocate the array, respectively. But note that this array must be freed explicitly with the according function HFree, HFreeLocal or HFreeTmp after usage. The behavior of the routines in case of passing array types different to the expected can be specified by the convert parameter according to the description in [section 5.5.1](#) on page 72.

| | | |
|--------------------------------------|--|---|
| Names | | |
| HGetCElemH1, HGetCElemH, HGetCElemHN | | |
| Synopsis | | |
| #include "Halcon.h" | | |
| HGetCElemH1(| Hproc_handle int H_HANDLE_TYPE const Hphandle | proc_handle, par, *htype, elem) |
| HGetCElemH(| Hproc_handle int H_HANDLE_TYPE const Hphandle INT4_8 | proc_handle, par, *htype, elem, *num) |
| HGetCElemHN(| Hproc_handle int H_HANDLE_TYPE const INT4_8 Hphandle | proc_handle, par, *htype, num, elem) |

Figure 5.28: Routines for reading handles by copy.



Note that HGetPPar automatically checks the result state of the underlying procedure similarly to the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HGetPPar** yourself.

5.5.6 HCopyElemL, HCopyElemD

HCopyElemL and HCopyElemD (see [figure 5.30](#)) read the parameter values of the input control parameter with the index par (1...n) and write them to the array elem that must have been allocated before with a suitable size (see HGetCParNum for information on getting the actual array length). According to the routine's suffix, HCopyElemL expects LONG_PAR, HCopyElemD DOUBLE_PAR arrays. The behavior of the routines in case of passing array types different to the expected can be specified by the convert parameter according to the description in [section 5.5.1](#) on page 72. The number of elements that have been allocated for elem must be passed to num. In return, num will hold the number of actually copied array indices.



Note that HCopyElemL and HCopyElemD automatically check the result state of the underlying procedure similarly to the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HCopyElemL and HCopyElemD** yourself.

5.5.7 HGetCPar

HGetCPar (see [figure 5.30](#)) reads the parameter values of the input control parameter with the index par (1...n) and writes them to the array val of Hcpar structures that must have been allocated before with a suitable size.



Note that HGetCPar automatically checks the result state of the underlying procedure similarly to the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HGetCPar** yourself.

For every input value, its type (LONG_PAR, DOUBLE_PAR, STRING_PAR) is also stored within the Hcpar structure. Thus, it is possible to pass different control data types within one control parameter of a HALCON operator. The current number of values is returned in num. HGetCPar allows to restrict the parameter access in two respects:

- The expected type can be specified by type. This also includes type combinations such as LONG_PAR | DOUBLE_PAR.
- The expected number of values can be specified by the interval (min,max), whereas max should not exceed the number of allocated Hcpar elements within the array val.

Names

HGetElemL, HGetElemD, HGetElemS

Conversion Flags

```

CONV_NONE /* no conversion; do only consider original element types */
CONV_CAST /* <INT4_8>=(INT4_8)<double>; <double>=(double)<INT4_8> */
CONV_IDNT /* convert double to INT4_8, if double has no fraction */
CONV_RND /* <INT4_8>=(INT4_8)(<double>+0.5) */

```

Synopsis

```

#include "Halcon.h"

HGetElemL(      Hproc_handle      proc_handle,
               int                par,
               int                convert,
               int                memtype,
               INT4_8 *restrict    *elem,
               INT4_8             *num)

HGetElemD(      Hproc_handle      proc_handle,
               int                par,
               int                convert,
               int                memtype,
               double *restrict    *elem,
               INT4_8             *num)

HGetElemS(      Hproc_handle      proc_handle,
               int                par,
               int                convert,
               int                memtype,
               char *restrict*restrict *elem,
               INT4_8             *num)

```

Figure 5.29: Routines for reading control input parameters by copy.

If the specified number or types of values are violated, HGetCPar exits the supply procedure with an appropriate error message. Figure 5.32 shows an application of HGetCPar.

Note that in case of string parameters, memory has to be allocated for `val[i].par.s`. The easiest way to do this is to use `HALlocStringMem` specifying the expected number of characters for *all* input strings, see section 5.5.10.

5.5.8 HGetSPar

HGetSPar is a simplified version of HGetCPar. In contrast to the latter, a *fixed* number of parameter values is read, see figure 5.33. Therefore, the routine does not return the actual number⁶ of values.

Note that HGetSPar automatically checks the result state of the underlying procedure similarly to the macro HCKP (see section 5.6.1 on page 83). Thus, **you must not use HCKP on HGetSPar yourself**.



5.5.9 HGetCParNum

HGetCParNum returns the length of input control arrays of the input control parameter with the index `par` ($1 \dots n$). This makes it possible to allocate exactly as much memory for parameter values as needed for reading them, for example, via `HCopyElemL`, `HCopyElemD`, or `HGetCPar`. As an alternative, you can use the reference passing routines as `HGetPElem` or `HGetPPar`, or routines as `HGetElemL` that allocate memory implicitly. Figure 5.34 shows an application of HGetCParNum.

⁶This number is fixed. If more or less values are passed to the HALCON operator, HGetSPar exits the supply procedure with an error.

Names

HCopyElemL, HCopyElemD, HGetCPar

Conversion Flags

```
CONV_NONE /* no conversion; do only consider original element types */
CONV_CAST /* <INT4_8>=(INT4_8)<double>; <double>=(double)<INT4_8> */
CONV_IDNT /* convert double to INT4_8, if double has no fraction */
CONV_RND /* <INT4_8>=(INT4_8)(<double>+0.5) */
```

Synopsis

```
#include "Halcon.h"
```

```
HCopyElemL(      Hproc_handle      proc_handle,
                 int                par,
                 int                convert,
                 INT4_8 *restrict    elem,
                 INT4_8              *num);
```

```
HCopyElemD(      Hproc_handle      proc_handle,
                 int                par,
                 int                convert,
                 double *restrict    elem,
                 INT4_8              *num);
```

```
HGetCPar(        Hproc_handle      proc_handle,
                 int                par,
                 int                type,
                 Hcpar              *val,
                 INT4_8              min,
                 INT4_8              max,
                 INT4_8              *num)
```

Figure 5.30: Routines for reading control input parameters by copy to a preallocated array.

```
INT4_8          l[10]; /* maximum array length of 10 */
INT4_8          num = 10;

/* read a short/int/long value in parameter 1 */
HCopyElemL(proc_handle,1,CONV_RND,1,&num);
/* now l == [2,4], num = 2 */
...
```

Figure 5.31: Read the parameter values [1.7,4] of control parameter 1 using HCopyElemL.



Note that HGetCParNum automatically checks the result state of the underlying procedure similarly to the macro HCkP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCkP on HGetCParNum** yourself.

5.5.10 HALlocStringMem

In case of string parameters, additional memory for the parameter values has to be allocated, because the Hcpar structure only contains a *pointer* to char. The easiest way to do this is to use HALlocStringMem specifying the expected number of characters for *all* input strings (parameter size) at the begin of a supply procedure, see [figure 5.32](#) and [figure 5.33](#). It is not necessary to free this memory explicitly — this is done automatically at the end of the supply procedure.



Note that HALlocStringMem automatically checks the result state of the underlying procedure using HCkP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCkP on HALlocStringMem** yourself.

```

Hcpar    par1,par2;
Hcpar    par3[10];

/* allocate memory for strings */
HAllocStringMem(proc_handle,1000);
/* read a short/int/long value in parameter 1 */
HGetCPar(proc_handle,1,LONG_PAR,&par1,1,1,&num);
/* now par1.par.l == 5 */
/* read a string in parameter 2 */
HGetCPar(proc_handle,2,STRING_PAR,&par2,1,1,&num);
/* now par2.par.s == "Text" */
/* read a tuple of float values in parameter 3 */
/* (max. 10 values) */
HGetCPar(proc_handle,3,DOUBLE_PAR,par3,1,10,&num);
for (i=0; i<num; i++) {
    /* par3[i].par.d == 0.5,1.7,4.4 */
    ...
}

```

Figure 5.32: Read the control parameter values of the operator call `demo(5,'Text',[0.5,1.7,4.4])` using `HGetCPar`.

```

Hcpar    par1,par2;
Hcpar    par3[3];

/* allocate memory for strings */
HAllocStringMem(proc_handle,1000);
/* read a short/int/long value in parameter 1 */
HGetSPar(proc_handle,1,LONG_PAR,&par1,1);
/* now par1.par.l == 5 */
/* read a string in parameter 2 */
HGetSPar(proc_handle,2,STRING_PAR,&par2,1);
/* now par2.par.s == "Text" */
/* read a tuple of 3 float values in parameter 3 */
HGetSPar(proc_handle,3,DOUBLE_PAR,par3,3);
for (i=0; i<num; i++) {
    /* par3[i].par.d == 0.5,1.7,4.4 */
    ...
}

```

Figure 5.33: Read the control parameter values of the operator call `demo(5,'Text',[0.5,1.7,4.4])` using `HGetSPar`.

5.5.11 HPutPElem

`HPutPElem` (see [figure 5.35](#) on page 81) writes a native array to the output control parameter with the index `par.val` holds the reference to the array of the according type, coded in `type` (`LONG_PAR` for arrays of type `INT4_8`, `DOUBLE_PAR`, for double, and `STRING_PAR` for `char*` arrays). The length of the array is passed in `num`. Instead of copying the array like `HPutElem` does, `HPutPElem` directly stores the pointer to the output control parameter and, thus, causes less overhead. Therefore, this array has to be allocated “permanently”, i.e. it must be allocated by using `HAlloc` (see [section 3.2.2](#) on page 43). Furthermore, the array must not be freed after passing it to `HPutPElem`. [Figure 5.36](#) shows how to write output control data with `HPutPElem`.

Note that `HPutPElem` automatically checks the result state of the underlying procedure similarly to the macro `HCKP` (see [section 5.6.1](#) on page 83). Thus, **you must not use `HCKP` on `HPutPElem` yourself**.



5.5.12 HPutPPar

`HPutPPar` (see [figure 5.35](#) on page 81) is an alternative to `HPutCPar` and writes control data to the output control parameter with the index `par`. However, instead of copying the `num` values like `HPutCPar` does, `HPutPPar` directly stores the pointer to the array of `Hcpar` structures (`val`). Thus, it causes less overhead. As `HPutPPar` directly uses the passed `Hcpar` array without copying, this array has to be allocated “permanently”, i.e. it must be allocated by

```

Hcpar    par1,par2;
Hcpar    *par3;
INT4_8   num;

/* allocate memory for strings */
HAllocStringMem(proc_handle,1000);
/* read a short/int/long value in parameter 1 */
HGetSPar(proc_handle,1,LONG_PAR,&par1,1);
/* now par1.par.l == 5 */
/* read a string in parameter 2 */
HGetSPar(proc_handle,2,STRING_PAR,&par2,1);
/* now par2.par.s == "Text" */
/* read a tuple of float values in parameter 3; */
/* first, get the number of values */
HGetCParNum(proc_handle,3,&num);
/* now num == 3 */
/* second, allocate memory for the values and read them */
HCKP(HAllocTmp(proc_handle,(void*)&par3,(size_t)(num*sizeof(Hcpar))));

HGetSPar(proc_handle,3,DOUBLE_PAR,par3,num);
for (i=0; i<num; i++) {
    /* par3[i].par.d == 0.5,1.7,4.4 */
    ...
}

```

Figure 5.34: Use `HGetCParNum` to get the number of control values before reading the control parameter values of the operator call `demo(5, 'Text', [0.5, 1.7, 4.4])`.

using `HAlloc` (see [section 3.2.2](#) on page 43). Furthermore, the array must not be freed after passing it to `HPutPPar`. [Figure 5.37](#) shows how to write output control data with `HPutPPar`.



Note that `HPutPPar` automatically checks the result state of the underlying procedure similarly to the macro `HCKP` (see [section 5.6.1](#) on page 83). Thus, **you must not use `HCKP` on `HPutPPar` yourself.**

As already mentioned, every data element may use a different type, because the types of the parameter values (`LONG_PAR`, `DOUBLE_PAR`, `STRING_PAR`) are stored with each `Hcpar` structure.

5.5.13 HPutElem

`HPutElem` (see [figure 5.35](#)) writes a native array to the output control parameter with the index `par` of a HALCON operator. The type of the array passed in `val` is coded by `type`, with `LONG_PAR` for arrays of type `INT4_8`, `DOUBLE_PAR`, for `double`, `STRING_PAR` for `char*` arrays. In contrast to `HPutPElem`, the values are *copied* by this routine.

5.5.14 HPutElemH

`HPutElemH` (see [figure 5.35](#)) writes `num` handle references to the output control parameter with the index `par` of a HALCON operator. `elem` points to an array that holds `num` elements. `HHandleInfo` contains information about the type of the corresponding handles. Most notably, `HHandleInfo` contains pointers to the functions that operate on the handles (`clear`, `serialize`, `deserialize` and `signal`).



Note that the output control variable gains ownership of all pointers that are in `elem`. When aborting an operator with an error, those values must not be cleared inside the operator's code, but will be cleared automatically when cleaning the output control variable.

5.5.15 HPutCPar

`HPutCPar` (see [figure 5.35](#)) writes control data to the output control parameter with the index `par` of a HALCON operator. The `num` values in the `Hcpar` structure `val` are *copied* by this routine. Because the types of the parameter

Names

HPutPElem, HPutPPar
 HPutElemH, HPutCPar

Synopsis

```
#include "Halcon.h"

/* --- writing output parameters by reference */
HPutPElem(      Hproc_handle  proc_handle,
                int           par,
                void          *val,
                INT4_8        num,
                int           type)

HPutPPar(       Hproc_handle  proc_handle,
                int           par,
                Hcpar         *val,
                INT4_8        num)

/* --- writing output parameters by copy */
HPutElem(       Hproc_handle  proc_handle,
                int           parnr,
                void const    *val,
                INT4_8        num,
                int           type)

HPutElemH(      Hproc_handle  proc_handle,
                int           par,
                void const    *elem,
                INT4_8        num,
                H_HANDLE_TYPE *HHandleInfo)

HPutCPar(       Hproc_handle  proc_handle,
                int           par,
                Hcpar const    *val,
                INT4_8        num)
```

Figure 5.35: Routines for writing control output parameters.

```
double *d;

HCKP(HA1loc(proc_handle, sizeof(*d)*2, &d));

d[0] = 1.2;
d[1] = 4.4;
HPutPElem(proc_handle, 1, d, 2, DOUBLE_PAR);
```

Figure 5.36: Write the control parameter values [1.2, 4.4] using HPutPElem.

values (LONG_PAR, DOUBLE_PAR, STRING_PAR) are stored with each Hcpar structure, you can use a different type for every data element, see [figure 5.38](#).

Note that HPutCPar automatically checks the result state of the underlying procedure similarly to the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HPutCPar** yourself.



```

Hcpar   *par;

HCkP(HALloc(proc_handle, (size_t)(sizeof(Hcpar)*2), (void**)&par));

par[0].par.l = 6;
par[0].type = LONG_PAR;
par[1].par.d = 4.4;
par[1].type = DOUBLE_PAR;
HPutPPar(proc_handle, 1, par, 2);

```

Figure 5.37: Write the control parameter values [6, 4.4] using HPutPPar.

```

Hcpar   par[2];

par[0].par.l = 6;
par[0].type = LONG_PAR;
par[1].par.d = 4.4;
par[1].type = DOUBLE_PAR;
HPutCPar(proc_handle, 1, par, 2);

```

Figure 5.38: Write the control parameter values [6, 4.4] using HPutCPar.

5.6 Auxiliary Extension Package Interface Macros and Procedures

In this section, a couple of auxiliary routines are described that facilitate the programming of supply or action procedures, see [figure 5.39](#).

Names

HCkP, HCkNoObj, HRLDecomp, HNumOfChannels, HIncrRL

Synopsis

```

#include "Halcon.h"

HCkP(           Herror           (*proc))

HCkNoObj(       Hproc_handle     proc_handle)

Herror HRLDecomp( Hrlregion const *reg_in,
                 int             r1,
                 int             c1,
                 int             r2,
                 int             c2,
                 Hrlregion       *reg_inner,
                 Hrlregion       *reg_outer)

HNumOfChannels( Hproc_handle     proc_handle,
                INT4_8           obj_index,
                int              *num_channels)

HError HIncrRL( Hproc_handle     proc_handle)

```

Figure 5.39: Auxiliary Extension Package Interface Macros and Procedures.

5.6.1 HCkP

The macro HCkP (see [figure 5.39](#)) checks the result state of a procedure call. Most of the HALCON procedures are of the type `Error`. For internal HALCON procedures, the result code `H_MSG_OK` is returned if no error occurred, see also [section 3.7](#) on page 47. HCkP exits the current procedure if the encapsulated procedure returns any other error code. Moreover, this error code is returned to the caller of the current procedure.

The macro is used to make source code more compact, but still safe with respect to error handling, see [figure 5.40](#): Here, the call of the procedure `HRLDecomp` is encapsulated within the macro. If any error occurs, the procedure exits with an appropriate error code. Otherwise the processing is continued.

Note that most of the interface routines described in this chapter internally call HCkP, i.e. they exit the current procedure returning an appropriate error code in case of an error.

Be aware that **all memory permanently allocated within a procedure will not be deallocated in case of an error** if you exit the procedure using HCkP. This will lead to memory leaks.



```

Error    err;

/* without HCkP: */
err = HRLDecomp(reg_in,r1,c1,r2,c2,
               reg_inner,reg_outer);
if (err != H_MSG_OK) return err;

/* with HCkP: */
HCkP(HRLDecomp(reg_in,r1,c1,r2,c2,
               reg_inner,reg_outer));

```

Figure 5.40: Error handling with HCkP.

5.6.2 HCkNoObj

The macro HCkNoObj (see [figure 5.39](#) on page 82) is used to check whether all iconic input parameters of an operator contain at least one iconic object. Otherwise, the supply procedure is exited with a return code depending on the current setting of `no_object_result` accessible by the HALCON operators `set_system` and `get_system` (see the Reference Manuals for details). The default setting for `no_object_result` is `H_MSG_TRUE`, that means HCkNoObj reports “no error” in case of empty iconic input parameters. Note that in this case all output parameters are also empty.

We recommend to call

```
HCkNoObj(proc_handle);
```

at the beginning of the supply procedure for every operator with iconic input objects to guarantee the existence of iconic data to be processed within the operator.

5.6.3 HRLDecomp

HRLDecomp (see [figure 5.39](#) on page 82) is an auxiliary procedure to ease border treatment within the action procedures of filter operators based on filter *masks*. It’s prototype is included in `hlib\HRLC1ip.h`.

The region (respectively domain or area of definition) `reg_in` of the image to be processed is split into two parts: `reg_inner` and `reg_outer`. Note that both new regions must have been allocated before, see [section 3.2.1](#) on page 41.

`reg_inner` is the original region `reg_in` minus the pixels around the image border. It contains all pixels within the rectangle specified by the upper left corner⁷ (`r1,c1`) and the lower right corner (`r2,c2`). These coordinates

⁷`r1` and `r2` denote *row* coordinates, `c1` and `c2` *column* coordinates.

```

Error IPBFilter(HBYTE      *in,          /* input image      */
               Hrlregion  *region,     /* domain (area of def.) */
               int        width,       /* image size: width  */
               int        height,     /* image size: height */
               HBYTE      *out)       /* output image      */
{
    ...
    Hrlregion *inner,*outer;

    HCkP(HALlocRLNumTmp(proc_handle,&inner,region->num));
    HCkP(HALlocRLNumTmp(proc_handle,&outer,region->num*2));
    HCkP(HRLDecomp(region,1,1,height-2,width-2,inner,outer));
    /* filtering without border treatment */
    for (i=0; i<inner->num; i++)
        for (k=CB(inner->rl,i,width); k<=CE(inner->rl,i,width); k++)
            out[k] = ...
    /* filtering with border treatment */
    for (i=0; i<outer->num; i++)
        for (k=CB(outer->rl,i,width); k<=CE(outer->rl,i,width); k++)
            out[k] = ...
    HCkP(HFreeRLTmp(proc_handle,outer));
    HCkP(HFreeRLTmp(proc_handle,inner));
}

```

Figure 5.41: Border treatment for a 3×3 filter.

should be selected that way, that the filter mask is completely *within* the image when placed on any pixel inside of the rectangle. Thus, no border treatment is necessary within `reg_in`.

`reg_out` is set to all remaining pixels within `reg_in`. For those pixels an appropriate (and time consuming) border treatment has to be performed. Figure 5.41 shows an application of `HRLDecomp`.



Note that `HRLDecomp` is no macro, i.e., it does not check the result state of the underlying procedure using `HCkP`. Thus, **you must call `HCkP` on `HRLDecomp` yourself** as shown in the example.

Note that the distinction of “inner” and “outer” area only refers to the *image border*, but not to the *border of the regions specifying the domain (area of definition)*. So, it is only ensured that no memory access to positions outside the image matrix can happen, but there is no guarantee that all pixel values covered by the filter mask when placed on pixels within `reg_inner` are *defined*, if they do not belong to `reg_in`. This means, a filter might use undefined gray values along the border of the domain of the input images. The HALCON user should keep that in mind, when applying a *sequence* of filters to restricted regions of interest.

5.6.4 HNumOfChannels

`HNumOfChannels` (see figure 5.39 on page 82) returns for the *first* input iconic parameter of a HALCON operator the number of channels of the image object with the index `obj_index`. Thus, this routine is just a shortcut for using `HPNumOfChannels` as defined in figure 5.5 on page 60 with `par_num = 1`.



Note that `HNumOfChannels` automatically checks the result state of the underlying procedure with the macro `HCkP`. Thus, **you must not use `HCkP` on `HNumOfChannels` yourself**.

5.6.5 HIncrRL

`HIncrRL` (see figure 5.39 on page 82) increases the value of the system parameter `'current_runlength_number'` by 50%, not exceeding $2 * (\text{width} + 1) * \text{height}$, where `width` and `height` are the dimensions of the largest image. These dimensions are accessible using `get_system` with `'width'` and `'height'` (see the Reference Manuals for details). Note, `DEF_RL_LENGTH` can also be increased using `set_system`.

As a consequence the procedures `HALlocRL` (page 44), `HALlocRLTmp` (page 42), and `HALlocRLLocal` (page 43) allocate regions of increased size. Figure 5.41 shows an application of `HIncrRL`.

Note that HIncrRL is no macro, i.e., it does not check the result state of the underlying procedure using HCKP. Thus, **you must call HCKP on HIncrRL yourself** as shown in the example.



```
Hrlregion  *region;
Herror     err;
HCKP(HAllocRLTmp(proc_handle, &region));
do
{
    /* Use HPGetURL instead of HGetURL, to perform explicit error handling. */
    err = HPGetURL(proc_handle, 1, region);
    if (err == H_ERR_WRRLN2)
    /* Number of chords too big, increase */
    {
        HCKP(HFreeUpToTmp(proc_handle, region));
        HCKP(HIncrRL(proc_handle));
        HCKP(HAllocRLTmp(proc_handle, &region));
    }
    else if (err != H_MSG_OK)
    {
        HCKP(HFreeRLTmp(proc_handle, region));
        return err;
    }
} while (err == H_ERR_WRRLN2);
```

Figure 5.42: Increasing memory allocated for regions.

Chapter 6

Special Routines for Typical Supply Procedures

In the previous chapter, the basic routines for handling iconic objects, iconic object parameters, and control parameters of a HALCON operator have been introduced. Based on these, this chapter describes a set of convenience routines that facilitate the programming of supply procedures in typical situations.

6.1 Loop Macros

A frequently needed task is to process all image objects (images or regions) passed to an operator by one or two input iconic object parameters. This is true for most filter and many segmentation operators. Loop macros provide a framework for this problem, see also [section 5.3](#) on page 65.

The following table contains an overview of all loop macros, their areas of application, and the provided image data. Their syntax is defined in [figure 6.1](#).

| Macro | Application | Image Data Provided |
|-------------|---|--|
| HALlReg | region shape features, region transformation, binary morphology | region data (Hrlregion) of input image object |
| HALlSegm | gray value features, segmentation | region and image data (Hrlregion and Himage) of input image object |
| HALlFilter | filter, image transformations | region and image data (Hrlregion and Himage) of input image object, image data structure (Himage) for image output object |
| HALlFilter2 | filter, segmentation, arithmetic with two input images | intersection of the regions of both input image objects (Hrlregion), the image data of both objects, and a image data structure (Himage) for the image output object |

All macros described in this section have in common that they implement a loop over all image objects within the **first** input iconic parameter. HALlFilter2 also includes a parallel loop over all objects within the second input object parameter. It is assumed that the operator does not have any more input iconic parameters. The macros provide users with the region (domain) and the pixel data of each image object so that they can work on the data within the loop. Some also create output image objects.

The macros return the index of the current object `obj_index` ($1 \dots n$) within the input iconic object parameter. Thus, `obj_index` can be seen as a reference parameter of the macro and therefore is notated¹ with `'&obj_index'`.

The macros return all regions as pointers to the original region data within the HALCON database. So the programmer is *only allowed to read* them. The only exception is again HALlFilter2 that computes the intersection of the region data of both input images and stores it in a new region.

¹Note that this is a specific notation only - do not pass pointers to the macros!

Names

HAllReg, HAllSegm, HAllFilter, HAllFilter2

Synopsis

```
#include "Halcon.h"
```

```
HAllReg(   Hproc_handle  proc_handle,
          Hrlregion    **region,
          INT4_8       obj_index)
```

```
HAllSegm( Hproc_handle  proc_handle,
          Hrlregion    **region,
          Himage       *image,
          int          max_channels,
          INT4_8       obj_index)
```

```
HAllFilter( Hproc_handle  proc_handle,
            Hrlregion    **region,
            Himage       *image_in,
            Himage       *image_out,
            int          max_channels,
            INT4_8       obj_index)
```

```
HAllFilter2( Hproc_handle  proc_handle,
             Hrlregion    *region,
             Himage       *image_in1,
             Himage       *image_in2,
             Himage       *image_out,
             int          max_channels,
             INT4_8       obj_index)
```

Figure 6.1: *Convenience* loop macros to access iconic objects. “&” denotes output parameters of the macros. This is only a special notation to make clear that these parameters are *changed* by the macros. So do *not* pass pointers to variables but the variables itself to the macro.

6.1.1 HAllReg

HAllReg (see [figure 6.1](#)) implements a loop over all iconic objects of the **first** input image parameter. For every object within this parameter, it returns the region of the iconic object (domain) in `region`². All gray value channels are ignored.

HAllReg is a combination of HAllObj (see [section 5.3.1](#) on page 66) and HGetFDRL (see [section 5.2.2](#) on page 62). It is typically used within feature extraction operators: A list of input regions have to be examined concerning special features. Some HALCON operators of this kind are e.g., [circularity](#), [area_center](#), or [contlength](#). Moreover, it is possible to return new region(s) by using the interface macro HNewRegion (see [section 6.2.1](#) on page 94) as it is done e.g., by [erosion_rectangle1](#) or [shape_trans](#).

[Figure 6.2](#) illustrates the application of HAllReg showing a complete supply procedure for a hypothetical operator `center` that computes the center of gravity of all input regions. The operator has one input iconic object parameter that exclusively contains regions and two output control parameters for returning the results as tuples of floating-point numbers (the coordinates of the centers of gravity of all regions). The corresponding DEF file (short version) might look like this:

```
center <- CIPCenter [Regions:::Rows$F,Columns$F];
```

`center` may be called with one or more regions as input. HAllReg implements a loop over all of them, sets the loop index `i` to the current index of the region ($1 \dots n$), and passes a pointer to the region to the action procedure that performs the center of gravity. In our case the action procedure is the internal HALCON procedure `HRLArea`. The result values are written into two arrays of the type `Hcpar` and returned by `HPutCPar` (see [section 5.5.15](#) on page 80).

²Remember: HALCON image objects consist of *one* region specifying the domain (area of definition) and an arbitrary number of gray value channels containing the pixel data


```

Herror CIPCenter(Hproc_handle proc_handle)
{
    Hcpar      *Row,*Col;
    INT4_8     num;
    double     row,col;
    INT4_8     area;
    INT4_8     i;
    Hrlregion  *region;

    /* allocate memory corresponding to the number of regions. */
    HGetObjNum(proc_handle,1,&num);
    HcKP(HAlloc(proc_handle,sizeof(*Row)*num,&Row);
    HcKP(HAlloc(proc_handle,sizeof(*Col)*num,&Col);
    /* get the regions of all input iconic objects in the first param. */
    HAllReg(proc_handle,&region,i)
    {
        HcKP(HRLArea(proc_handle,region,&area,&row,&col));
        Row[i-1].type = DOUBLE_PAR;      /* par. type is float */
        Row[i-1].par.d = row;             /* resulting row */
        Col[i-1].type = DOUBLE_PAR;      /* par. type is float */
        Col[i-1].par.d = col;            /* resulting column */
    }
    HPutPPar(proc_handle,1,Row,i);      /* return result */
    HPutPPar(proc_handle,2,Col,i);      /* return result */
    return(H_MSG_TRUE);
}

```

Figure 6.2: An application of HAllReg: Compute the center of gravity for all input regions in the *first* input iconic object parameter.

6.1.2 HAllSegm

HAllSegm (see [figure 6.1](#)) extends HAllReg: Not only the region but also all gray value channels of an object within the **first** input image object parameter are accessed within a loop. Thus, HAllSegm is a combination/modification of HAllObj (see [section 5.3.1](#) on page 66), HGetFDRL (see [section 5.2.2](#) on page 62), and HAllComp (see [section 5.3.2](#) on page 66). It is especially useful for segmentation operators (transition of gray value channels to regions). Some typical HALCON operators that make use of HAllSegm are [threshold](#), [regiongrowing](#), [auto_threshold](#), or [label_to_region](#).

A HALCON image object (in short a HALCON *image*) consists of *one* region (domain) that specifies its area of definition and of *one or more* channels (gray value components) containing the pixel data. All channels of an image are of the same size, but may have different pixel types. The data contained in a channel (pixel type, the image matrix, etc.) is stored in a structure of type Himage (see [section 4.1](#) on page 49). If the image has only one channel, the address of a variable of the type Himage is passed to HAllSegm. For multi-channel images an array of the type Himage [max_channels] must be passed. The maximal number of channels to be accessed by HAllSegm is specified by the parameter max_channels, see [figure 6.3](#).

```

Himage      images[3];
HAllSegm(proc_handle,region,images,3,i) {
    ...
Himage      image;
HAllSegm(proc_handle,region,&image,1,i) {
    ...

```

Figure 6.3: The parameters image and max_channels of HAllSegm.

The parameter max_channels only specifies the *maximum* number of channels. If an image contains less channels, the corresponding Himage elements in the image array are undefined. The actual number of channels can be accessed e.g., using HNumOfChannels (see [section 5.6.4](#) on page 84). An image must contain at least *one* channel. Otherwise, HAllSegm returns an error. If the number of channels exceeds max_channels, the remaining channels

are ignored. Furthermore, the size of all channels is checked for equality³.

```

Error IPSegm(Hproc_handle proc_handle, /* HALCON proc. handle */
            Hrlregion *region, /* domain (area of definition) */
            Himage *image, /* input image */
            Hrlregion *out) /* segmentation result */
{
    /* compute region "out" from "region" and "image" */
    return(H_MSG_OK);
}

Error CIPSegm(Hproc_handle proc_handle)
{
    INT4_8 i;
    Hrlregion *region, *new_region;
    Himage image;

    HcKp(HAllocRLTmp(proc_handle,&new_region)); /* allocate memory*/
    HAllSegm(proc_handle,&region,&image,1,i) { /* all inp. images*/
        HcKp(IPSegm(region,&image,new_region));
        HNewRegion(proc_handle,new_region); /* allocate new */
    } /* region */
    HcKp(HFreeRLTmp(proc_handle,new_region)); /* free memory */
    return(H_MSG_TRUE);
}

```

Figure 6.4: A typical application of HAllSegm: A segmentation operator.

Figure 6.4 shows a framework for a supply procedure for a segmentation operator using HAllSegm. The corresponding hypothetical operator `segm` has one input object parameter for input images containing at least one channel. The DEF file (short version) might look like

```
segm <- CIPSegm[Image:Region:];
```

The macro HAllSegm used in CIPSegm performs a loop over all image objects within the first input object parameter `Image` of `segm`. With every pass of the loop it returns the image data of the current input object in the variables `region` (domain) and `image` (first gray value channel). The results of the segmentation (`new_region`) are stored via the macro HNewRegion (see section 6.2.1 on page 94) as new objects of the HALCON database and returned in the (first) output object parameter (`Region`). Note that this simple operator has no control parameters.

A new region is allocated for the action procedure via HAllocRLTmp (see section 3.2.1 on page 41) before entering the loop. This region is used as temporary memory for the computation result and must be deallocated (via HFreeRLTmp) before exiting the supply procedure.

6.1.3 HAllFilter

HAllFilter (see figure 6.1 on page 88) further extends the loop macros introduced so far: For every input image object a new output image object is created (and added to the first output object parameter) with

- the same number of channels (components),
- the same pixel type (of the corresponding channels),
- the same image size and
- the same area of definition (region, domain).

Thus, HAllFilter is a combination/modification of HAllObj (see section 5.3.1 on page 66), HGetFDRL (see section 5.2.2 on page 62), HAllComp (see section 5.3.2 on page 66), HCopyObj (see section 5.4.2 on page 68), and HPutDImage (see section 5.4.6 on page 70). It has been designed for filter operators that typically create a modified result image for every input image. The region remains unmodified. Typical examples for this functionality are the HALCON operators `sobel_amp`, `mean_image`, `scale_image_max`, or `texture_laws`.

³Remember: The sizes must be equal, whereas the pixel types of different channels may vary

```

Error IPScaleNew(Hrlregion      *region,
                Himage         *image_in,
                Himage         *image_out,
{
    INT4_8 i,l,end;
    double h;

    for (i=0; i<region->num; i++) {
        end = CE(region->rl,i,image_in->width);
        for (l=CB(region->rl,i,image_in->width); l<=end; l++) {
            HDFImage(h,image_in,l);
            HImageFD(image_out,h*mult,l);
        }
    }
    return(H_MSG_OK);
}

Error CIPScaleNew(Hproc_handle proc_handle)
{
    Hcpar      mult;
    Hrlregion  *region;
    Himage     image_in,image_out;
    INT4_8     i;

    HGetSPar(proc_handle,1,DOUBLE_PAR,&mult,1);
    HALIFilter(proc_handle,&region,&image_in,&image_out,1,i) {
        HCKP(IPScaleNew(region,&image_in,mult.par.d,&image_out));
    }
    return(H_MSG_TRUE);
}

```

Figure 6.5: A typical application of HALIFilter: A filter operator.

Figure 6.5 shows a typical application of HALIFilter – a hypothetical operator `scale_new` that multiplies all gray values of the input objects within the **first** input object parameter with a constant. The corresponding DEF file (short version) might look like

```
scale_new <- CIPScaleNew[Image:ImageScaled:Mult:$f:];
```

The operator has one input object parameter (`Image`) that contains one or more input image objects (each consisting of one or more gray value channels and one region as domain, i.e., area of definition). With every pass of the loop an image object is accessed and its components are transferred to `region` and `image_in`, see also HALISegm in section 6.1.2 on page 89. These components are passed to the action procedure `IPScaleNew`. In this example only the first channel of each input object is used.

HALIFilter also creates output objects (in the HALCON database) to return the modified data. Furthermore, these objects are added to the list of objects for the first output object parameter (here `ImageScaled`). Their underlying image matrices are accessible via `image_out`. Those are also passed to the action procedure `IPScaleNew` within the loop. `IPScaleNew` calculates the new gray values for all pixels within the domain of the input image and writes them into the provided image components `image_out`⁴. The regions of the image objects remain unmodified so that all pixels of output objects lying outside the region are undefined.

Note that HALIFilter creates all necessary image matrices, combines them with the input regions to new image objects, and returns those in the first output object parameter. So the programmer of the supply procedure needs not to bother about the handling of image objects etc. To access the input control parameter, `HGetSPar` (see section 5.5.8 on page 77) is used in the example.

The structure `image_in` may contain different pixel types. There are several ways to handle this within an operator:

1. The simplest method is to implement the operator just for the most common pixel type `BYTE_IMAGE` and return an error message (`H_ERR_WIT`) for any other pixel type.

⁴Note that `image_out` contains a pointer to a pixel matrix with the same size and pixel type as `image_in`.

2. Another way is to provide several action procedures – one for every pixel type – and call the appropriate procedure via `switch(image_in.kind)`.
3. The third (generic) method makes use of the macros `HDFImage` and `HImageFD`, see [figure 6.6](#). They encapsulate the access to gray values by buffering them in a double variable.

By writing pixel values via `HImageFD`, the double value `val` is converted into the current pixel type of `image_in` (and therefore may be clipped) and stored in the pixel specified by the linear coordinate `lin_coord`, see [section 4.1](#) on page 49.

The other way around, the specified pixel value is converted to double and returned in `val` when using `HDFImage` to read image data.

The third method has been used in our example, as it allows a very compact source code. But this variant naturally shows drawbacks in terms of computation time: Two type conversions have to be computed with every pixel access and all pixel arithmetic has to be done in double.

```

Names

HDFImage, HImageFD

Synopsis

#include "Halcon.h"

HDFImage( double      &val,
          Himage      *image,
          INT4_8      lin_coord)

HImageFD( Himage      *image,
          double      val,
          INT4_8      lin_coord)

```

Figure 6.6: Auxiliary macros for generic access to pixel data. “&” denotes an output parameter of `HDFImage`. This is only a special notation to make clear that this parameter is *changed* by the macro. So do *not* pass a pointer to double but the double variable itself to the macro.

6.1.4 HAllFilter2

The macro `HAllFilter2` (see [figure 6.1](#) on page 88) is a variation of `HAllFilter` introduced in the previous section. It facilitates the implementation of filters with *two* input object parameters. Examples for this technique are the HALCON operators `add_image`, `mult_image`, `bit_and`, and `max_image`.

`HAllFilter2` extends `HAllFilter` so that with every image object of the first input object parameter also the corresponding image object (with the same object index `obj_index`) of the second input object parameter is provided. Moreover, it checks the image sizes of both image objects for equality. If the sizes are equal, the images are provided in the loop variables `image_in1` and `image_in2`, otherwise an error is returned.

Moreover, `HAllFilter2` computes a *new* input region (`region`) by intersecting the domains (areas of definition) of both input images. Note that memory for this region must have been allocated before (e.g. with `HALlocRLTmp`). Furthermore, `region` must be deallocated at the end of the supply procedure (`HFreeRLTmp`).

Output image objects are created and returned in the first output object parameter in the same way as described for `HAllFilter` in [section 6.1.3](#) on page 90.

[Figure 6.7](#) shows a typical application of `HAllFilter2` – the implementation of an operator that adds the gray values of two input images. As in procedure `IPScaleNew` in [figure 6.5](#) on page 91, the macros `HDFImage` and `HImageFD` are used to read and write pixel values. This example exhibits the additional advantage that the operator can even add the gray values of two images with *different* pixel types.

6.2 Object Generation

This section describes the *convenience* routines `HNewRegion`, `HPutRect`, and `HDupObj` for creating new image objects, see [figure 6.8](#).

```

Herror IPAddNew(Hproc_handle proc_handle,
               Hrlregion    *region,
               Himage       *image_in1,*image_in2,*image_out)
{
    INT4_8 i,l,end;
    double h1,h2;

    for (i=0; i<region->num; i++) {
        end = CE(region->r1,i,image_in->width);
        for (l=CB(region->r1,i,image_in->width); l<=end; l++) {
            HDFImage(h1,image_in1,l);
            HDFImage(h2,image_in2,l);
            HImageFD(image_out,h1+h2,l);
        }
    }
    return(H_MSG_OK);
}

Herror CIPAddNew(Hproc_handle proc_handle)
{
    Hrlregion    *region;
    Himage       image_in1,image_in2,image_out;
    INT4_8       i;

    HCkP(HAllocRLTmp(proc_handle,&region));
    HAllFilter2(proc_handle,region,&image_in1,
               &image_in2,&image_out,1,i) {
        HCkP(IPAddNew(proc_handle,region,&image_in1,
                     &image_in2,&image_out));
    }
    HCkP(HFreeRLTmp(proc_handle,region));
    return(H_MSG_TRUE);
}

```

Figure 6.7: A typical application of HAllFilter2.

HNewRegion creates a new image object in the HALCON database encapsulating the specified region and adds this object to the first output object parameter. HPutRect inserts a rectangular region (as domain, i.e., area of definition) into an already existing output image object. Finally, HDupObj adds an iconic input object to the object list of the first output object parameter.

Names

HNewRegion, HPutRect, HDupObj

Synopsis

```
#include "Halcon.h"
```

```
HNewRegion(Hproc_handle proc_handle,
           Hrlregion    *region)
```

```
HPutRect( Hproc_handle proc_handle,
          Hkey         obj_key,
          HIMGDIM      width,height)
```

```
HDupObj( Hproc_handle proc_handle,
         INT4_8       obj_index)
```

Figure 6.8: Convenience routines for creating output objects.

6.2.1 HNewRegion

HNewRegion (see [figure 6.8](#)) is used to create a new image object in the HALCON database which is also added to the first output object parameter. It contains a copy of `region`. It is common to call an image object *region*, when only its region component is used.



Note that HNewRegion automatically checks the result state of the underlying procedure with the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HNewRegion** yourself.

```

Error CIPConvex(Hproc_handle proc_handle)
{
  Hrlregion *region;
  Hrlregion *region_new;

  HCKP(HAllocRLTmp(proc_handle,&region_new) /* allocate memory */
  HAllReg(proc_handle,&region,i) { /* all regions */
    HCKP(HRLConvex2(proc_handle,region,region_new));
    /* create an output region object (first output param.) */
    HNewRegion(proc_handle,region_new);
  }
  HCKP(HFreeRLTmp(proc_handle,region_new)); /* free memory */
  return(H_MSG_TRUE);
}

```

Figure 6.9: A typical application of HNewRegion: The region transformation “convex hull”.

Typically, HNewRegion is used within segmentation procedures (see [figure 6.4](#) on page 90) and region transformation procedures such as the procedure CIPConvex shown in [figure 6.9](#). CIPConvex corresponds to a hypothetical operator `trans_convex` which might be defined as

```
trans_convex <- CIPConvex[Region:RegionConvex::];
```

In the example, all regions within `Region` are provided in `region` by `HAllReg` (see [section 6.1.1](#) on page 88) one after the other. The internal HALCON procedure `HRLConvex2` computes the convex hull for each region and writes it to `region_new`. Furthermore, a new region object in the HALCON database is created and added to the output object parameter `RegionConvex`.

Note that HNewRegion was also used in the example in [figure 6.4](#) on page 90.

6.2.2 HPutRect

HPutRect (see [figure 6.8](#) on page 93) inserts a rectangular region in an already existing output object with database key `obj_key`. It is mostly used in connection with operators that create *new* image objects like in the example in [figure 6.10](#).



Note that HPutRect automatically checks the result state of the underlying procedure with the macro HCKP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCKP on HPutRect** yourself.

Note that HCrObj (see [section 5.4.1](#) on page 67) creates an object with *empty* region. In many situations the default domain (area of definition) for a new image will be the full image domain, which is a rectangle. In this situation the use of HPutRect is very convenient.

6.2.3 HDupObj

HDupObj (see [figure 6.8](#) on page 93) is a combination/simplification of HGetObj (see [section 5.1.1](#) on page 57) and HCopyObj (see [section 5.4.2](#) on page 68). It duplicates iconic input objects (images, regions, XLD) in order to pass them directly to the **first** output object parameter. The objects to be duplicated are specified by their index `obj_index` within the **first** input object parameter. Note that this index corresponds to `obj_index` as defined for

```

Herror CIOGrabImage(Hproc_handle proc_handle)
{
    Hkey   obj_key, image_key;
    Himage image;


    HCrObj(proc_handle, 1, &obj_key);
    HCkP(HNewImage(proc_handle, &image, BYTE_IMAGE, 640, 480));
    /* grab an NTSC image 640 x 480 pixel, 8 bit */
    HCkP(IOBGrabImage(&image));
    HPutDImage(proc_handle, obj_key, 1, &image, false, &image_key);
    HPutRect(proc_id, obj_key, image.width, image.height);
    return(H_MSG_TRUE);
}

```

Figure 6.10: A typical application of HPutRect: Grabbing an image.

the loop macros (HAll*) in [section 6.1](#) on page 87. HDupObj is typically used for operators that examine objects and select them by a given criterion. Some HALCON operators of this kind are [select_shape](#) or [select_gray](#).

Note that HDupObj automatically checks the result state of the underlying procedure with the macro HCkP (see [section 5.6.1](#) on page 83). Thus, **you must not use HCkP on HDupObj yourself**.

[Figure 6.11](#) shows an application of HDupObj: CIPUserSelect computes the length of the contour of each input region (in parameter 1). All regions with a contour of at least the minimal length min are passed to the output. 

```

Herror CIPUserSelect(Hproc_handle proc_handle)
{
    Hrlregion *region;
    Hrlregion *region_new;
    double length;
    Hcpar min;
    INT4_8 i;

    HGetSPar(proc_handle, 1, DOUBLE_PAR, &min, 1); /* get min. length */
    HAllReg(proc_handle, &region, i) { /* all regions */
        HCkP(HRLContLength(proc_handle, region, &length)); /* length */
        if (length >= min.par.d) /* length o.k. ? */
            HDupObj(proc_handle, i); /* duplicate object*/
    }
    return(H_MSG_TRUE);
}

```

Figure 6.11: A typical application of HDupObj: Duplicate input regions that fulfill a specific criteria (length of contour).

Since HDupObj only increases the number of references to a database object instead of copying it physically, its memory costs and computational costs are neglectable. In contrast, e.g., HNewRegion and HAllFilter always allocate new memory for the output objects. So whenever possible, HDupObj should be used.

Chapter 7

Creating a New HALCON Package

This chapter explains step by step how to create a new package. Note that the description often references the environment variable `HALCONARCH`, which is set during the installation. For more details about this variable please refer to the Installation Guide, [section 1.4](#) on page 8.

7.1 The HALCON Compiler `hcomp`

The HALCON compiler `hcomp` is the most important tool for creating a new HALCON package. It automatically generates the interface code for the desired host language, the help files, and the documentation files. `hcomp` processes DEF files that contain descriptions of all operators as a basic resource, see [chapter 2](#) on page 19. The HALCON compiler uses the same mechanism for generating the original system operators and user-defined operators.

The syntax of the `hcomp` command is as follows:

```
hcomp <options> <files>
```

Example:

```
hcomp -u -H -ppackage MyUserOps.def
```

The parameter “-u” signals that an interface for user-defined operators should be generated. This parameter can be omitted as it is the default¹. The option `-H` generates the main package interface code (`Hpackage.c`). One or more definition files that are separated by blanks must be specified as files argument. The extension `.def` may be omitted:

```
hcomp -C -ppackage MyUserOps1 MyUserOps2 MyUserOps3
```

You either call `hcomp` in the directory of the DEF files (typically the package subdirectory `def`) or specify the path to the DEF files.

To use the package in a programming language, you must also generate the appropriate interface code. In the example above, the corresponding C files (`HCpackage.c` and `HCpackage.h`) are created with the option `-C`. Their names depend on the host language and the specified package, not on the names of the input DEF files.

7.1.1 Selection of the Host Language

One call of `hcomp` can always create only one interface, i.e, the options described as follows can only be switched on under mutual exclusion. Use

¹Note that `hcomp` also is used by MVTec to generate the interface code for the normal HALCON system.

```
hcomp -H [-ppackage] <DEF files>
```

to create the main interface code (`Hpackage.c`), which is necessary independent whether you want to use the package in HDevelop or in a programming language.

Additionally, the commands in the following table create the needed files for the corresponding programming languages.

| Language | Command | Created Files |
|----------|---|--|
| C | <code>hcomp -C [-ppackage] <DEF files></code> | <code>HCpackage.c</code> <code>HCpackage.h</code> |
| C++ | <code>hcomp -P [-ppackage] <DEF files></code> | <code>HCPPpackage.cpp</code> <code>HCPPpackage.h</code> |
| C# | <code>hcomp -N [-ppackage] <DEF files></code> | <code>HDOTNETpackage.cs</code> |

The generated source files are the basis for the interface libraries, see [section 7.2](#) on page 100.

7.1.2 Creating the Help Files

Help files are necessary for the online access to the operator knowledge base via HALCON operators like `get_operator_info`. For example, HDevelop uses their information to build up the menu tree 'Operator' (chapter and section structuring) and 'Suggestions' (alternatives, cross references, predecessor, successor, and keywords). The help files are generated for the language selected with the (optional) `-l` option. The default language is English.

```
hcomp -M -l<language> <DEF files>
```

creates files with the stem `operators_`, followed by the language (default: `en_US`), and the following extensions:

| Extension | Description |
|-------------------|--|
| <code>.ref</code> | The operator description (text, value lists, ...). |
| <code>.idx</code> | Index for every operator specifying the start address of its entry within the <code>*.ref</code> file. |
| <code>.key</code> | List of keywords (index entries) with the associated operators. |
| <code>.num</code> | Specification of the number of parameters per parameter class for every operator. |
| <code>.sta</code> | Specification of the parameter names and the chapter names for every operator. |

In addition to the option `-M`

```
-c<TAGS-FILE>
```

can be set in order to insert the source file and the line number of the supply procedure of the operator into the `*.ref` file. To do this, a *TAGS-File* (usually TAGS) must have been generated by the `etags` command before.

7.1.3 Creating HTML Reference Files

`hcomp` can generate HTML reference files. Thus, its easy to provide an online documentation of new operators that can be accessed with an HTML browser. Use

```
hcomp -R [-p<package>] -l<lang> -a<author-info> -f<copyright-footer> <DEF files>
```

to create HTML files. Note that the created HTML files contain the information for all programming language interfaces.

With the (optional) parameters `-a` and `-f` you can customize the created manual: The author information passed with the parameter `-a` appears on the main HTML page; the string passed with the parameter `-f` appears at the bottom of every generated HTML page.

The following files are generated:

- `index.html`
Home page containing the chapter structure and links to the different (sub-)chapters (`toc_<chapter>_<subchapter>.html`)
- `index_by_name.html`
Alphabetical list of all operators with links to the corresponding operator description pages (files `<operator>.html`)
- `index_classes.html`
List of all classes (for .NET) with links to the corresponding description pages (files `<class>.html`)
- `toc_<chapter>_<subchapter>.html`
For every (sub-)chapter: A list of all operators within the chapter with links to the corresponding operator description pages (files `<operator>.html`)
- `<operator>.html`
A description page for each operator
- `<class>.html`
A description page for each class (for .NET)

7.1.4 Creating the PDF Reference Manuals

`hcomp` can also generate \LaTeX files containing the complete reference manuals adapted to the different supported programming languages, i.e. the description of the operators is provided in a specific syntax. Use

```
hcomp -Rlatex:<plang> [-p<package>] -l<lang> -a<author-info> -f<copyright-footer> <DEF files>
```

to create \LaTeX files. *plang* can be set to `c`, `cpp`, `com`, `dotnet`, and `hdevelop` (HDevelop syntax). `hdevelop` is default and may therefore be omitted. The package name specified with `[-p]` is used for the title page of the manual.

The information passed with the parameter `-a` appears in the PDF version of the manual (see below) in the field “Author” of the dialog describing the document. With the parameter `-f` you can pass a string, which then appears on the back side of the title page. A typical use of this parameter is to print a copyright notice.

The generated \LaTeX files use the package `halcon_reference_en_US.sty` (or similar for other languages). This package resides in the directory `$HALCONROOT/doc/macros` (Linux notation). You must include this directory in the environment variable `TEXINPUTS`. If the variable is empty, set it to:

```
:$HALCONROOT/doc/macros
```

Otherwise, \LaTeX will be unable to find it (typical error message: File ‘`halcon_reference_en_US.sty`’ not found).

The \LaTeX file(s) can be transformed into PDF files by using `pdflatex` and `makeindex`. Note that `pdflatex` must be called several times to get the references right; to get a correct table of context and index the sequence of calls is `pdflatex > pdflatex > makeindex > pdflatex > pdflatex`.

The generated PDF contains interactive bookmarks and hyperlinks similar to the HTML version (and the author information passed with the parameter `-a`). Note that this functionality requires that your \LaTeX distribution includes the package `hyperref`; if this package exists but is too old, a warning will be issued, as this can result in errors during the \LaTeX process or in suboptimal PDFs.

For a printer-friendly variant of the PDF file, you can disable the interactive features by modifying the file `index.tex` before starting `pdflatex`: Replace the line (possibly with different language key)

```
\usepackage[pdflinks]{halcon_reference_en_US}
```

by

```
\usepackage{halcon_reference_en_US}
```

If you want to create both documents with and without PDF links, please use different directories or remember to delete all auxiliary \LaTeX files before starting to `pdflatex` the modified `index.tex`, because the two versions are not compatible.

7.1.5 Miscellaneous

Here are some more options supported by `hcomp`:

| Option | Description |
|--|--|
| <code>hcomp -i filename <DEF files></code> | Consider only the operators listed in <i>filename</i> . |
| <code>hcomp -x filename <DEF files></code> | Do <i>not</i> consider the operators listed in <i>filename</i> . |

7.2 Generating HALCON Packages

Once the new operators have been described in DEF files and implemented (supply and action procedures) a couple of dynamic objects (DLLs in Windows, shared libraries in Linux environments, respectively) must be created. **Never change the name of a package or the corresponding names of the libraries/DLLs contained in a package.** These names are encoded *within* the libraries. If you change the names this information will not match any longer. Thus, the loader of the operating system will fail to open the dynamic libraries. If you want to rename a package, you must *create* the libraries/DLLs again.

To activate a package, its complete path must be added to the environment variable `HALCONEXTENSIONS`, e.g.,

```
%HALCONEXAMPLES%\extension_package\halconuser
```

Please note that the package paths in `HALCONEXTENSIONS` are separated by semicolons (Windows) or colons (Linux), see also [section 1.3](#) on page 13.

7.2.1 Creating the Operator Libraries

The supply and action procedures must be encapsulated in a DLL (Windows), shared library (Linux). The name of this shared object must be consistent with the package name (plus file extension). For the use by HALCON XL, a second version of the library must be created, with the additional suffix `x1` to the name. Please refer to [section 7.2.6](#) and the documentation of your programming environment for more details (also about the following sections).

Under Windows the generated DLLs must be placed in the subdirectory `bin\%HALCONARCH%`, the libraries in the subdirectory `lib\%HALCONARCH%`. Under Linux, the generated shared libraries must be placed in the subdirectory `lib/$HALCONARCH`, binaries in the subdirectory `bin/$HALCONARCH` of the package. .NET assemblies must be placed in the subdirectory `bin\dotnet`.

Independent of whether you want to use the package in HDevelop or in a programming language, you must create the main interface library package. This library is based on a single C file `Hpackage.c`, which is generated via

```
hcomp -H -ppackage <DEF file(s)>
```

7.2.2 Creating the C Interface

To access new HALCON operators inside a package within C programs, you must create a C interface library `packagec` residing in the subdirectory `lib\%HALCONARCH%` of the package. This library is based on a single C file `HCpackage.c`, which is generated via

```
hcomp -C -ppackage <DEF file(s)>
```

from the DEF files of your new operators. Note that `hcomp` simultaneously generates the file `HCpackage.h` containing the C prototypes of your new operators. Include this file in your C programs using these operators.

7.2.3 Creating the C++ Interface

To access new HALCON operators inside a package within C++ programs you must create a C++ interface library `packagecpp` residing in the subdirectory `lib\%HALCONARCH%` of the package. This library is based on the file `HCPPpackage.cpp` generated via

```
hcomp -P -ppackage <DEF file(s)>
```

from the DEF files of your self developed operators. Note that `hcomp` simultaneously generates the file `HCPPpackage.h` containing the C++ prototypes of your new operators. Include this file in your C++ programs using these operators.

7.2.4 Creating the .NET Interface

To access new HALCON operators inside a package within .NET programs, you must create the interface assembly `packagedotnet` residing in the subdirectory `lib\dotnet` of the package. This assembly is based on the C# source file `HDOTNETpackage.cs`, which is generated via

```
hcomp -N -ppackage <DEF file(s)>
```

from the DEF files of your new operators.

7.2.5 Creating New Applications

To create new application programs (written in C, C++, or .NET languages) based on your own HALCON operators, you must link the corresponding language interface libraries `packagec` or `packagecpp` to your objects, or reference the corresponding .NET assembly `packagedotnet`. For C or C++ applications, you furthermore need the HALCON library itself and the HALCON/C or HALCON/C++ library (as for any HALCON application). For .NET applications, you need the HALCON/.NET assembly.

7.2.6 Additional Information for Specific Platforms

The previous sections summarized the generation of HALCON extensions in general. This section contains additional information for specific platforms. The main differences concern the name handling and the generation of shared libraries / DLLs.

7.2.6.1 Generating Packages Under Windows

To activate a package, its complete path, e.g.,

```
%HALCONEXAMPLES%\extension_package\halconuser
```

must be included in the environment variable `HALCONEXTENSIONS`. In the Windows version the package paths in `HALCONEXTENSIONS` are separated by semicolons.

Note that DLLs must be stored in the subdirectory `bin\%HALCONARCH%` of the package, the corresponding libraries in the subdirectory `lib\%HALCONARCH%`.

- **Creating object files for the HALCON XL version:**

By default, using `CMakeLists.txt`, the package will be built with the normal version of HALCON. If you want to build with HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step. For this, use the following syntax:

```
cmake -DHALCON_XL=1 %HALCONEXAMPLES%\extension_package\halconuser
```

- **Creating the operator DLL** `package.dll` and the library `package.lib`:

To create the operator DLL `package.dll` containing new HALCON operators and the corresponding library `package.lib`, the object files containing the corresponding supply and action procedures and the HALCON library `halcon.lib` must be linked.

To create the libraries `packagexl.dll` and `packagexl.lib` for HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step. The corresponding object files must be linked to the HALCON XL library `halconxl.lib` instead of `halcon.lib`.

- **Creating the C interface DLL** `packagec.dll` and the library `packagec.lib`:

To create the libraries `packagec.dll` and `packagec.lib`, which provide the C interface to new HALCON operators, the object file `HCpackage.obj`, the new operator library `package.lib`, the HALCON C library `halconc.lib`, and the HALCON library `halcon.lib` must be linked.

To create the libraries `packagecxl.dll` and `packagecxl.lib` for HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step. The corresponding object files must be linked to the HALCON XL version of the libraries, i.e., `packagecxl.lib`, `halconcxl.lib`, and `halconxl.lib`.

- **Creating the C++ interface DLL** `packagecpp.dll` and the library `packagecpp.lib`:

To create the DLL `packagecpp.dll` providing the C++ interface to new HALCON operators and the corresponding library `packagecpp.lib`, the object file `HCPPpackage.obj`, the new operator library `package.lib`, the HALCON C++ library `halconcpp.lib` and the HALCON library `halcon.lib` must be linked.

To create the libraries `packagecppxl.dll` and `packagecppxl.lib` for HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step. The corresponding object files must be linked to the HALCON XL version of the libraries, i.e., `packagecxl.lib`, `halconcppxl.lib`, and `halconxl.lib`.

- **Creating the .NET interface assembly** `packagedotnet.dll`:

The assembly `packagedotnet.dll` providing the .NET interface to new HALCON operators is created directly from the source file `HDOTNETpackage.cs`, together with the XML file that documents the content of the assembly.

To create the assembly `packagedotnetxl.dll` for HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step.

- **Creating new applications:**

To create new application programs written in C or C++, you must link `packagec.lib` or `packagecpp.lib` to your objects. Furthermore, you will need `halconc.lib` or `halconcpp.lib` (as for any HALCON application). For .NET applications, you reference the libraries `packagec.lib` and `halconx.lib` or the assemblies `packagedotnet.dll` and `halcondotnet.dll`, respectively.

To create a HALCON XL version of your application, just use the HALCON XL version of the libraries (e.g., `packagecxl.lib` and `halconcxl.lib` in case of a C application).

To be able to link the package DLL to your application program, the *complete* DLL file path of the new package, e.g.,

```
%HALCONEXAMPLES%\extension_package\halconuser\bin\%HALCONARCH%
```

has to be added to the environment variable `PATH`. This is also true for .NET applications.

Do not copy a package DLL into the Windows system directories, as it would be loaded twice in this case!

If you encounter program crashes, **check the stack size** allocated by your application. A stack size of 6 to 8 MB is recommended.

The directory `%HALCONEXAMPLES%\extension_package\halconuser` contains the example CMake file `CMakeLists.txt`, which can be used to create the example package `halconuser` and the example applications based on the package `halconuser`. If required, download CMake (version 3.7.1 or later) from the [CMake website](#) and install it. To build the example package `halconuser` using CMake, do the following:

```
mkdir build
cd build
cmake -DCMAKE_INSTALL_PREFIX=%HALCONEXAMPLES%\extension_package \
      HALCONEXAMPLES%\extension_package\halconuser
cmake --build . --target install
```

By default, the normal version of HALCON is created. If you want to build using HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step.

7.2.6.2 Generating Packages Under Linux

To activate a package, its complete path, e.g.,

```
$HALCONEXAMPLES/extension_package/halconuser
```

must be included in the environment variable `HALCONEXTENSIONS`. In the Linux version, the package paths in `HALCONEXTENSIONS` are separated by colons. Please see also the comments on installing a HALCON package on a Linux system in [section 1.3.2](#) on page 14.

- **Compiling the source code:**

To generate shared libraries, you must produce position-independent code. For the `gcc/g++` compiler, this is done using the option `-fPIC`. For `gcc`, we also recommend the options `-march=pentium` `-mcpu=pentiumpro` `-ansi` `-fno-strict-prototype`.

- **Creating object files for the HALCON XL version:**

By default, using `CMakeLists.txt`, the package will be built with the normal version of HALCON. If you want to build with HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step. For this, use the following syntax:

```
cmake -DHALCON_XL=1 %HALCONEXAMPLES%\extension_package\halconuser
```

- **Creating the operator library `libpackage.so`:**

To create the operator library `libpackage.so` containing new HALCON operators, the object files containing the corresponding supply and action procedures must be linked. The linkage of shared libraries is done with `ld -shared`. Specify the desired name `libpackage.so` and location of the library with the `ld` option `-o`.

To create the library `libpackagexl.so` for HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step. The corresponding object files must be linked.

- **Creating the C interface library `libpackagec.so`:**

To create the C interface library `libpackagec.so` providing the interface to new HALCON operators, the object file `HCPackage.o` and the new operator library `libpackage.so` must be linked.

To create the library `libpackagecxl.so` for HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step. The corresponding object file must be linked to the HALCON XL version of the operator library, i.e., `libpackagexl.so`.

- **Creating the C++ interface library `libpackagecpp.so`:**

To create the C++ interface library `libpackagecpp.so` providing the interface to new HALCON operators, the object files `HCPPpackage.o` and `HCPPpackageGlobal.o`, and the new operator library `libpackage.so` must be linked.

To create the library `libpackagecppxl.so` for HALCON XL, set the option `HALCON_XL` to `ON` or `1` in CMake during the configuration step. The corresponding object files must be linked to the HALCON XL version of the operator library, i.e., `libpackage.so`.

- **Creating the .NET interface assembly `packagedotnet.dll`:**

You can use the Mono compiler to create the assembly `packagedotnet.dll` providing the .NET interface to new HALCON operators. This assembly is based on the C# source file `HDOTNETpackage.cs`, see [section 7.2.4](#) on page 101. Note that you need a successfully installed and configured version of Mono to create the assembly.

For this, run the following commands in a shell:

```
mcs HDOTNETpackage.cs /target:library /out:Hpackage.dll /doc:Hpackage.xml /warn:1 -r:halcondotnet.dll
```

To create an executable you have to reference the new created assembly `Hpackage.dll` and the HALCON .NET assembly as well.

- **Creating new applications:**

To create new application programs written in C or C++, you must link `libpackage.so` and `libpackagec.so` or `libpackagecpp.so` to your objects (besides `libhalcon.so` and `libhalconc.so` or `libhalconcpp.so` as for any HALCON application). For .NET applications, you reference the assemblies `packagedotnet.dll` and `halcondotnet.dll`.

Furthermore, you must add the package library subdirectory `lib/$HALCONARCH` to the environment variable `LD_LIBRARY_PATH`.

To create a HALCON XL version of your application, just use the HALCON XL version of the libraries (e.g., `libpackagexl.so`, `libpackagecxl.so`, `libhalconxl.so`, and `libhalconcxl.so` in case of a C application).

7.3 HALCON Directories

HALCON always presumes that the environment variable `HALCONROOT` contains the path of the HALCON installation directory. The following subdirectories are important for creating a new system:

- `include`
HALCON include files for compiling
- `lib\%HALCONARCH%`
HALCON libraries
- `dotnet20,dotnet35`
HALCON/.NET assemblies for the different versions of the .NET Framework (for more information, see the Programmer's Guide, [table 10.1](#) on page 64)
- `bin\%HALCONARCH%`
HALCON compiler `hcomp`, under Windows also the HALCON DLLs
- `doc\macros`
L^AT_EX files for generating PDF reference files or manuals

The environment variable `HALCONEXAMPLES` contains the path of the HALCON programming examples. The following subdirectory is useful for creating a new system:

- `extension_package\halconuser`
Example for a HALCON extension package

Appendix A

HALCON Error Codes

In this section all HALCON error codes are summarized, see also [section 3.7](#) on page 47.

| Error Name | Code | Description |
|--------------|------|-------------------------------------|
| H_ERR_WIPT1 | 1201 | Wrong type of control parameter 1 |
| H_ERR_WIPT2 | 1202 | Wrong type of control parameter 2 |
| H_ERR_WIPT3 | 1203 | Wrong type of control parameter 3 |
| H_ERR_WIPT4 | 1204 | Wrong type of control parameter 4 |
| H_ERR_WIPT5 | 1205 | Wrong type of control parameter 5 |
| H_ERR_WIPT6 | 1206 | Wrong type of control parameter 6 |
| H_ERR_WIPT7 | 1207 | Wrong type of control parameter 7 |
| H_ERR_WIPT8 | 1208 | Wrong type of control parameter 8 |
| H_ERR_WIPT9 | 1209 | Wrong type of control parameter 9 |
| H_ERR_WIPT10 | 1210 | Wrong type of control parameter 10 |
| H_ERR_WIPT11 | 1211 | Wrong type of control parameter 11 |
| H_ERR_WIPT12 | 1212 | Wrong type of control parameter 12 |
| H_ERR_WIPT13 | 1213 | Wrong type of control parameter 13 |
| H_ERR_WIPT14 | 1214 | Wrong type of control parameter 14 |
| H_ERR_WIPT15 | 1215 | Wrong type of control parameter 15 |
| H_ERR_WIPT16 | 1216 | Wrong type of control parameter 16 |
| H_ERR_WIPT17 | 1217 | Wrong type of control parameter 17 |
| H_ERR_WIPT18 | 1218 | Wrong type of control parameter 18 |
| H_ERR_WIPT19 | 1219 | Wrong type of control parameter 19 |
| H_ERR_WIPT20 | 1220 | Wrong type of control parameter 20 |
| H_ERR_WIPV1 | 1301 | Wrong value of control parameter 1 |
| H_ERR_WIPV2 | 1302 | Wrong value of control parameter 2 |
| H_ERR_WIPV3 | 1303 | Wrong value of control parameter 3 |
| H_ERR_WIPV4 | 1304 | Wrong value of control parameter 4 |
| H_ERR_WIPV5 | 1305 | Wrong value of control parameter 5 |
| H_ERR_WIPV6 | 1306 | Wrong value of control parameter 6 |
| H_ERR_WIPV7 | 1307 | Wrong value of control parameter 7 |
| H_ERR_WIPV8 | 1308 | Wrong value of control parameter 8 |
| H_ERR_WIPV9 | 1309 | Wrong value of control parameter 9 |
| H_ERR_WIPV10 | 1310 | Wrong value of control parameter 10 |
| H_ERR_WIPV11 | 1311 | Wrong value of control parameter 11 |
| H_ERR_WIPV12 | 1312 | Wrong value of control parameter 12 |
| H_ERR_WIPV13 | 1313 | Wrong value of control parameter 13 |
| H_ERR_WIPV14 | 1314 | Wrong value of control parameter 14 |
| H_ERR_WIPV15 | 1315 | Wrong value of control parameter 15 |
| H_ERR_WIPV16 | 1316 | Wrong value of control parameter 16 |
| H_ERR_WIPV17 | 1317 | Wrong value of control parameter 17 |
| H_ERR_WIPV18 | 1318 | Wrong value of control parameter 18 |

| Error Name | Code | Description |
|-----------------------------|------|---|
| H_ERR_WIPV19 | 1319 | Wrong value of control parameter 19 |
| H_ERR_WIPV20 | 1320 | Wrong value of control parameter 20 |
| H_ERR_WCOMP | 1350 | Wrong value of component (see reset_obj_db()) |
| H_ERR_WGCOMP | 1351 | Wrong value of gray value component (see reset_obj_db()) |
| H_ERR_WIPN1 | 1401 | Wrong number of values of control parameter 1 |
| H_ERR_WIPN2 | 1402 | Wrong number of values of control parameter 2 |
| H_ERR_WIPN3 | 1403 | Wrong number of values of control parameter 3 |
| H_ERR_WIPN4 | 1404 | Wrong number of values of control parameter 4 |
| H_ERR_WIPN5 | 1405 | Wrong number of values of control parameter 5 |
| H_ERR_WIPN6 | 1406 | Wrong number of values of control parameter 6 |
| H_ERR_WIPN7 | 1407 | Wrong number of values of control parameter 7 |
| H_ERR_WIPN8 | 1408 | Wrong number of values of control parameter 8 |
| H_ERR_WIPN9 | 1409 | Wrong number of values of control parameter 9 |
| H_ERR_WIPN10 | 1410 | Wrong number of values of control parameter 10 |
| H_ERR_WIPN11 | 1411 | Wrong number of values of control parameter 11 |
| H_ERR_WIPN12 | 1412 | Wrong number of values of control parameter 12 |
| H_ERR_WIPN13 | 1413 | Wrong number of values of control parameter 13 |
| H_ERR_WIPN14 | 1414 | Wrong number of values of control parameter 14 |
| H_ERR_WIPN15 | 1415 | Wrong number of values of control parameter 15 |
| H_ERR_WIPN16 | 1416 | Wrong number of values of control parameter 16 |
| H_ERR_WIPN17 | 1417 | Wrong number of values of control parameter 17 |
| H_ERR_WIPN18 | 1418 | Wrong number of values of control parameter 18 |
| H_ERR_WIPN19 | 1419 | Wrong number of values of control parameter 19 |
| H_ERR_WIPN20 | 1420 | Wrong number of values of control parameter 20 |
| H_ERR_IONTB | 1500 | Number of input objects too big |
| H_ERR_WION1 | 1501 | Wrong number of values of object parameter 1 |
| H_ERR_WION2 | 1502 | Wrong number of values of object parameter 2 |
| H_ERR_WION3 | 1503 | Wrong number of values of object parameter 3 |
| H_ERR_WION4 | 1504 | Wrong number of values of object parameter 4 |
| H_ERR_WION5 | 1505 | Wrong number of values of object parameter 5 |
| H_ERR_WION6 | 1506 | Wrong number of values of object parameter 6 |
| H_ERR_WION7 | 1507 | Wrong number of values of object parameter 7 |
| H_ERR_WION8 | 1508 | Wrong number of values of object parameter 8 |
| H_ERR_WION9 | 1509 | Wrong number of values of object parameter 9 |
| H_ERR_OONTB | 1510 | Number of output objects too big |
| H_ERR_BREAK | 20 | Operator canceled by user |
| H_ERR_WNP | 2000 | Wrong specification of parameter (error in file: xxx.def) |
| H_ERR_HONI | 2001 | Initialize HALCON: reset_obj_db(Width,Height,Components) |
| H_ERR_WRKNN | 2002 | Used number of symbolic object names too big |
| H_ERR_LIC_NO_LICENSE | 2003 | No license found |
| H_ERR_LIC_NO_MODULES | 2005 | No modules in license (invalid VENDOR_STRING) |
| H_ERR_LIC_NO_LIC_OPER | 2006 | No license for this operator |
| H_ERR_LIC_BADPLATFORM | 2008 | Vendor keys do not support this platform |
| H_ERR_LIC_BADVENDORKEY | 2009 | Bad vendor keys |
| H_ERR_LIC_BADSYSDATE | 2021 | System clock has been set back. This error can only occur when the FEATURE line contains an expiration date |
| H_ERR_LIC_BAD_VERSION | 2022 | Invalid format for version argument |
| H_ERR_LIC_CANTCONNECT | 2024 | Cannot establish a connection with a license server |
| H_ERR_LIC_MAXSESSIONS | 2028 | Maximum session limit reached |
| H_ERR_LIC_MAXUSERS | 2029 | All licenses in use |
| H_ERR_LIC_NO_SERVER_IN_FILE | 2030 | No license server specified for floating license |
| H_ERR_LIC_NOFEATURE | 2031 | Can not find feature in the license file |
| H_ERR_LIC_OLDVER | 2033 | License file does not support a version this new |
| H_ERR_LIC_PLATNOTLIC | 2034 | This platform not authorized by license - running on platform not included in PLATFORMS list |

| Error Name | Code | Description |
|-----------------------------------|------|---|
| H_ERR_LIC_SERVBUSY | 2035 | License server busy - the request should be retried (this is a rare occurrence) |
| H_ERR_LIC_NOCONFFILE | 2036 | could not find license file |
| H_ERR_LIC_BADFILE | 2037 | Invalid license file syntax |
| H_ERR_LIC_NOSERVER | 2038 | Cannot connect to a license server |
| H_ERR_LIC_NOTTHISHOST | 2041 | Invalid host |
| H_ERR_LIC_LONGGONE | 2042 | Feature has expired |
| H_ERR_LIC_BADDATE | 2043 | Invalid date format in license file |
| H_ERR_LIC_BADCOMM | 2044 | Invalid returned data from license server |
| H_ERR_LIC_BADHOST | 2045 | Cannot resolve server name |
| H_ERR_LIC_CANTWRITE | 2047 | Cannot write data to license server |
| H_ERR_LIC_SERVLONGGONE | 2051 | License server does not support this version of this feature |
| H_ERR_LIC_TOOMANY | 2052 | Request for more licenses than this feature supports |
| H_ERR_LIC_CANTFINDERETHER | 2055 | Cannot find ethernet device |
| H_ERR_LIC_NOREADLIC | 2056 | Cannot read license file |
| H_ERR_LIC_DATE_TOOBIG | 2067 | Date too late for binary format |
| H_ERR_LIC_NOSERVRESP | 2069 | Server did not respond to message |
| H_ERR_LIC_SETSOCKFAIL | 2075 | setsockopt() failed |
| H_ERR_LIC_BADCHECKSUM | 2076 | Message checksum failure |
| H_ERR_LIC_INTERNAL_ERROR | 2082 | Internal licensing error |
| H_ERR_LIC_NOSERVCAP | 2087 | Server does not support this request |
| H_ERR_LIC_POOL | 2091 | This feature is available in a different license pool |
| H_ERR_HEN_CANCEL | 21 | Operator canceled |
| H_ERR_WOOPI | 2100 | Wrong index for output object parameter |
| H_ERR_WIOPI | 2101 | Wrong index for input object parameter |
| H_ERR_WOI | 2102 | Wrong index for image object (too big or too small) |
| H_ERR_WRCN | 2103 | Wrong number region/image component (see: HGetComp) |
| H_ERR_WRRN | 2104 | Wrong relation name |
| H_ERR_AUDI | 2105 | Access to undefined gray value component |
| H_ERR_WIWI | 2106 | Wrong image width |
| H_ERR_WIHE | 2107 | Wrong image height |
| H_ERR_ICUNDEF | 2108 | Undefined gray value component |
| H_ERR_CANCEL | 22 | Operator canceled by interrupt_operator |
| H_ERR_IDBD | 2200 | Inconsistent data of data base (typing) |
| H_ERR_WICPI | 2201 | Wrong index for input control parameter |
| H_ERR_DBDU | 2202 | Data of data base not defined (internal error) |
| H_ERR_PNTL | 2203 | Number of operators too big |
| H_ERR_UEXTNI | 2205 | User extension not properly installed |
| H_ERR_NPTL | 2206 | Number of packages too large |
| H_ERR_NSP | 2207 | No such package installed |
| H_ERR_ICHV | 2211 | Incompatible HALCON versions |
| H_ERR_ICOI | 2212 | Incompatible operator interface |
| H_ERR_XPKG_WXID | 2220 | Wrong extension package id |
| H_ERR_XPKG_WOID | 2221 | Wrong operator id |
| H_ERR_XPKG_WOIID | 2222 | Wrong operator information id |
| H_ERR_TIMEOUT_BREAK | 23 | Operator canceled by user set timeout |
| H_ERR_LIC_NODONGLE | 2300 | Dongle not attached, or can't read dongle |
| H_ERR_LIC_NODONGLEDRIIVER | 2301 | Missing Dongle Driver |
| H_ERR_LIC_TIMEOUT | 2318 | Timeout |
| H_ERR_LIC_INVALID_CERTIFICATE | 2321 | License server certificate invalid |
| H_ERR_LIC_INVALID_TLS_CERTIFICATE | 2335 | License server SSL/TLS certificate invalid |
| H_ERR_LIC_BAD_ACTREQ | 2339 | Invalid activation request received |
| H_ERR_LIC_NOT_ALLOWED | 2345 | Specified operation is not allowed |
| H_ERR_LIC_ACTIVATION | 2348 | Activation error |
| H_ERR_LIC_NO_CM_RUNTIME | 2379 | No CodeMeter Runtime installed (version 6.30 or later required) |

| Error Name | Code | Description |
|------------------------------|------|--|
| H_ERR_LIC_CM_RUNTIME_TOO_OLD | 2380 | Installed version of CodeMeter Runtime is too old (version 6.30 or later required) |
| H_ERR_LIC_WRONG_EDITION | 2381 | License is for wrong edition of HALCON |
| H_ERR_LIC_UNKNOWN_FLAGS | 2382 | License contains unknown FLAGS |
| H_ERR_LIC_PREVIEW_EXPIRED | 2383 | HALCON preview version expired |
| H_ERR_LIC_NEWVER | 2384 | License file does not support a version this old |
| H_ERR_CTPL_WTYP | 2400 | Wrong Hctuple element type |
| H_ERR_CPAR_WTYP | 2401 | Wrong Hcpar parameter type |
| H_ERR_CTPL_WIDX | 2402 | Wrong Hctuple index |
| H_ERR_WFV | 2403 | Unsupported file version |
| H_ERR_WRONG_HANDLE_TYPE | 2404 | Invalid handle type |
| H_ERR_WVTYP | 2410 | Wrong vector type |
| H_ERR_WVDIM | 2411 | Wrong vector dimension |
| H_ERR_WHDL | 2450 | Wrong (unknown) HALCON handle |
| H_ERR_WID | 2451 | Wrong HALCON id, no data available |
| H_ERR_IDOOR | 2452 | HALCON id out of range |
| H_ERR_HANDLE_NULL | 2453 | HALCON handle is NULL |
| H_ERR_HANDLE_CLEARED | 2454 | HALCON handle was already cleared |
| H_ERR_HANDLE_NOSER | 2455 | HALCON handle of this type cannot be serialized |
| H_ERR_HANDLE_CYCLES | 2456 | Cyclic references of handles were detected |
| H_ERR_WT_CTRL_EXPECTED | 2460 | Type mismatch: expected control value, got iconic value |
| H_ERR_WT_ICONIC_EXPECTED | 2461 | Type mismatch: expected iconic value, got control value |
| H_ERR_XPI_INIT_NOT_CALLED | 2500 | Init function of an HALCON extension that was build with the hlibxpi interface was not called (check for correct hlibxpi export) |
| H_ERR_XPI_NO_INIT_FOUND | 2501 | Init function of the required HALCON extension was not found (old interface without hlibxpi support or the hlibxpi export failed) |
| H_ERR_XPI_UNRES | 2502 | Function call in HALCON extension couldn't be resolved via hlibxpi |
| H_ERR_XPI_HLIB_TOO_OLD | 2503 | The version of the HALCON library is too old for the required HALCON extension |
| H_ERR_XPI_XPI_TOO_OLD | 2504 | The required HALCON extension uses an hlibxpi version that is no longer supported by the current HALCON version |
| H_ERR_XPI_MAJOR_TOO_SMALL | 2505 | The current HALCON version uses an hlibxpi version that is not supported by the required HALCON extension (major number too small) |
| H_ERR_XPI_MINOR_TOO_SMALL | 2506 | The current HALCON version uses an hlibxpi version that is not supported by the required HALCON extension (minor number too small) |
| H_ERR_XPI_INT_WRONG_MAJOR | 2507 | Internal error: wrong version number in hlibxpi symbol list |
| H_ERR_XPI_UNKNOW_HLIB_VER | 2508 | hlibxpi cannot connect to hlib: unknown hlib version |
| H_ERR_HW_WFF | 2800 | Wrong hardware knowledge file format |
| H_ERR_HW_WFV | 2801 | Wrong hardware knowledge file version |
| H_ERR_HW_RF | 2802 | Error while reading the hardware knowledge |
| H_ERR_HW_WF | 2803 | Error while writing the hardware knowledge |
| H_ERR_HW_TF | 2804 | Tag in hardware knowledge file not found |
| H_ERR_HW_CPU | 2805 | No CPU information in hardware knowledge file found |
| H_ERR_HW_AOP | 2806 | No aop information in hardware knowledge file found |
| H_ERR_HW_HVAR | 2807 | No aop information for this HALCON variant found |
| H_ERR_HW_HARCH | 2808 | No aop information for this HALCON architecture found |
| H_ERR_HW_HOP | 2809 | No aop information for specified Operator found |
| H_ERR_HW_WAOPM | 2810 | Unknown aop model |
| H_ERR_HW_WTD | 2811 | Wrong tag derivate in hardware knowledge file |
| H_ERR_HW_IE | 2812 | Internal error while processing hardware knowledge |
| H_ERR_HW_CANCEL | 2813 | Optimizing aop was canceled |
| H_ERR_GV_WA | 2830 | Wrong access to global variable |
| H_ERR_GV_NC | 2831 | Used global variable does not exist |

| Error Name | Code | Description |
|-------------------------|------|---|
| H_ERR_GV_NG | 2832 | Used global variable not accessible via GLOBAL_ID |
| H_ERR_HM_NT | 2835 | HALCON server to terminate is still working on a job |
| H_ERR_HM_NA | 2837 | No such HALCON software agent |
| H_ERR_AG_CN | 2838 | Hardware check for parallelization not possible on a single-processor machine |
| H_ERR_AG_NC | 2839 | Sequential HALCON does not support parallel hardware check (use Parallel HALCON instead) |
| H_ERR_AG_IN | 2840 | Initialization of agent failed |
| H_ERR_AG_NT | 2841 | Termination of agent failed |
| H_ERR_AG_HW | 2842 | Inconsistent hardware description file |
| H_ERR_AG_II | 2843 | Inconsistent agent information file |
| H_ERR_AG_IK | 2844 | Inconsistent agent knowledge file |
| H_ERR_AG_WV | 2845 | The file with the parallelization information does not match to the currently HALCON version/revision |
| H_ERR_AG_WH | 2846 | The file with the parallelization information does not match to the currently used machine |
| H_ERR_AG_KC | 2847 | Inconsistent knowledge base of HALCON software agent |
| H_ERR_AG_CT | 2848 | Unknown communication type |
| H_ERR_AG_MT | 2849 | Unknown message type for HALCON software agent |
| H_ERR_AG_WK | 2850 | Error while saving the parallelization knowledge |
| H_ERR_AG_WW | 2851 | Wrong type of work information |
| H_ERR_AG_WA | 2852 | Wrong type of application information |
| H_ERR_AG_WE | 2853 | Wrong type of experience information |
| H_ERR_AG_NU | 2854 | Unknown name of HALCON software agent |
| H_ERR_AG_NE | 2855 | Unknown name and communication address of HALCON software agent |
| H_ERR_AG_RR | 2856 | CPU representative (HALCON software agent) not reachable |
| H_ERR_AG_CR | 2857 | CPU refuses work |
| H_ERR_AG_RN | 2858 | Description of scheduling resource not found |
| H_ERR_AG_TILT | 2859 | Not accessible function of HALCON software agent |
| H_ERR_WRT | 2860 | Wrong type: HALCON scheduling resource |
| H_ERR_WRS | 2861 | Wrong state: HALCON scheduling resource |
| H_ERR_UNKPT | 2862 | Unknown parameter type: HALCON scheduling resource |
| H_ERR_UNKPARVAL | 2863 | Unknown parameter value: HALCON scheduling resource |
| H_ERR_CTRL_WPP | 2864 | Wrong post processing of control parameter |
| H_ERR_GETTI | 2867 | Error while trying to get time (time query) |
| H_ERR_GETCPUNUM | 2868 | Error while trying to get the number of processors |
| H_ERR_TMPFNF | 2869 | Error while accessing temporary file |
| H_ERR_MQCNCNCL | 2890 | Message queue wait operation canceled |
| H_ERR_MQOVL | 2891 | Message queue overflow |
| H_ERR_MQCLEAR | 2892 | Threads still wait on message queue while clearing it |
| H_ERR_M_WRFIL | 2893 | Invalid file format for a message |
| H_ERR_DICT_KEY | 2894 | Dictionary does not contain requested key |
| H_ERR_DICT_TUPLE_LENGTH | 2895 | Tuple in dictionary has incorrect length |
| H_ERR_DICT_TUPLE_TYPE | 2896 | Tuple in dictionary is of incorrect type |
| H_ERR_PTHRD_SCHED | 2900 | Error while forcing a context switch |
| H_ERR_SCHED_GAFF | 2901 | Error while accessing the CPU affinity |
| H_ERR_SCHED_SAFF | 2902 | Error while setting the CPU affinity |
| H_ERR_CO_WSO | 2950 | Wrong synchronization object |
| H_ERR_CO_WOCO | 2952 | Wrong thread object |
| H_ERR_CO_IOPNI | 2953 | Input Object was not initialized |
| H_ERR_CO_ICPNI | 2954 | Input control parameter is not initialized |
| H_ERR_CO_OOPNI | 2955 | Output Object parameter is not initialized |
| H_ERR_CO_OCPNI | 2956 | Output control parameter is not initialized |
| H_ERR_PTHRD_CR | 2970 | creation of pthread failed |
| H_ERR_PTHRD_DT | 2971 | pthread-detach failed |
| H_ERR_PTHRD_JO | 2972 | pthread-join failed |

| Error Name | Code | Description |
|------------------|------|---|
| H_ERR_PTHRD_MI | 2973 | Initialization of mutex variable failed |
| H_ERR_PTHRD_MD | 2974 | Deletion of mutex variable failed |
| H_ERR_PTHRD_ML | 2975 | Lock of mutex variable failed |
| H_ERR_PTHRD_MU | 2976 | Unlock of mutex variable failed |
| H_ERR_PTHRD_CS | 2977 | Failed to signal pthread condition variable |
| H_ERR_PTHRD_CW | 2978 | Failed to wait for pthread condition variable |
| H_ERR_PTHRD_CI | 2979 | Failed to init pthread condition variable |
| H_ERR_PTHRD_CD | 2980 | Failed to destroy pthread condition variable |
| H_ERR_PTHRD_ES | 2981 | Failed to signal event |
| H_ERR_PTHRD_EW | 2982 | Failed to wait for an event |
| H_ERR_PTHRD_EI | 2983 | Failed to init an event |
| H_ERR_PTHRD_ED | 2984 | Failed to destroy an event |
| H_ERR_PTHRD_TSDC | 2985 | Failed to create a tsd key |
| H_ERR_PTHRD_TSDS | 2986 | Failed to set a tsd key |
| H_ERR_PTHRD_TSDG | 2987 | Failed to get a tsd key |
| H_ERR_PTHRD_TSDF | 2988 | Failed to free a tsd key |
| H_ERR_PTHRD_BA | 2989 | Aborted waiting at a barrier |
| H_ERR_DCDG_FLE | 2990 | 'Free list' is empty while scheduling |
| H_ERR_MSG_PNCI | 2991 | Communication partner not checked in |
| H_ERR_MSG_CSAI | 2992 | You can not start the communication system while running it |
| H_ERR_MSG_CSNI | 2993 | Communication partner not checked in |
| H_ERR_PTHRD_BI | 2994 | Failed to init a barrier |
| H_ERR_PTHRD_BW | 2995 | Failed to wait at a barrier |
| H_ERR_PTHRD_BD | 2996 | Failed to destroy a barrier |
| H_ERR_RCOIMA | 3010 | Region completely outside of the image domain |
| H_ERR_ROOIMA | 3011 | Region (partially) outside of the definition range of the image |
| H_ERR_RIEI | 3012 | Intersected definition range region / image empty |
| H_ERR_EDEF | 3013 | Image with empty definition range (=> no gray values) |
| H_ERR_IIEI | 3014 | No common image point of two images |
| H_ERR_FLTS | 3015 | Wrong region for image (first row < 0) |
| H_ERR_LLTB | 3016 | Wrong region for image (column in last row >= image width) |
| H_ERR_UENOI | 3017 | Number of images unequal in input parameters |
| H_ERR_HTS | 3018 | Image height too small |
| H_ERR_WTS | 3019 | Image width too small |
| H_ERR_CHSEG | 3020 | Internal error: multiple call of HRLInitSeg() |
| H_ERR_RLSEG1 | 3021 | Internal error: HRLSeg() not initialized |
| H_ERR_WGAUSSM | 3022 | Wrong size of filter for Gauss |
| H_ERR_FSEIS | 3033 | Filter size exceeds image size |
| H_ERR_FSEVAN | 3034 | Filter size have to be odd |
| H_ERR_FSTOBIG | 3035 | Filter is too big |
| H_ERR_EMPREG | 3036 | Input region is empty |
| H_ERR_DOM_DIFF | 3037 | Domains of the input images differ |
| H_ERR_ROWTB | 3040 | Row value of a coordinate > 2 ³⁰ -1 |
| H_ERR_ROWTS | 3041 | Row value of a coordinate < -2 ³⁰ +1 |
| H_ERR_COLTB | 3042 | Column value of a coordinate > 2 ³⁰ -1 |
| H_ERR_COLTS | 3043 | Column value of a coordinate < -2 ³⁰ +1 |
| H_ERR_WRTHR | 3100 | Wrong segmentation threshold |
| H_ERR_UNKF | 3101 | Unknown feature |
| H_ERR_UNKG | 3102 | Unknown gray value feature |
| H_ERR_EINCC | 3103 | Internal error in HContCut |
| H_ERR_EINCP1 | 3104 | Error in HContToPol: distance of points too big |
| H_ERR_EINCP2 | 3105 | Error in HContToPol: contour too long |
| H_ERR_TMR | 3106 | Too many rows (IPImageTransform) |
| H_ERR_SFZ | 3107 | Scaling factor = 0.0 (IPImageScale) |
| H_ERR_OOR | 3108 | Wrong range in transformation matrix |
| H_ERR_NEF | 3109 | Internal error in IPvfvf: no element free |

| Error Name | Code | Description |
|-------------------|------|--|
| H_ERR_NOOB | 3110 | Number of input objects is zero |
| H_ERR_EMPOB | 3111 | At least one input object has an empty region |
| H_ERR_NPOT | 3112 | Operation allowed for rectangular images 2**n only |
| H_ERR_TMEP | 3113 | Too many relevant points (IPHysteresis) |
| H_ERR_LTB | 3114 | Number of labels in image too big |
| H_ERR>NNLA | 3115 | No labels with negative values allowed |
| H_ERR_WFS | 3116 | Wrong filter size (too small?) |
| H_ERR_IWDS | 3117 | Images with different image size |
| H_ERR_IWTL | 3118 | Target image too wide or too far on the right |
| H_ERR_IWTS | 3119 | Target image too narrow or too far on the left |
| H_ERR_IHTL | 3120 | Target image too high or too far down |
| H_ERR_IHTS | 3121 | Target image too low or too far up |
| H_ERR_DNOC | 3122 | Number of channels in the input parameters are different |
| H_ERR_WRCFAFLT | 3123 | Wrong color filter array type |
| H_ERR_WRCFAINT | 3124 | Wrong color filter array interpolation |
| H_ERR_NO_AFFTRANS | 3125 | Homogeneous matrix does not represent an affine transformation |
| H_ERR_INPNOBDRY | 3126 | Inpainting region too close to the image border |
| H_ERR_DSIZESD | 3127 | Source and destination differ in size |
| H_ERR_TMFEAT | 3128 | To many Features |
| H_ERR_AXIS_UNDEF | 3129 | Reflection axis undefined |
| H_ERR_COWTS | 3131 | Cooccurrence matrix: too little columns for quantization |
| H_ERR_COHTS | 3132 | Cooccurrence matrix: too little rows for quantization |
| H_ERR_NUM_COLMN | 3133 | Wrong number of columns |
| H_ERR_NUM_LINES | 3134 | Wrong number of rows |
| H_ERR_OVL | 3135 | Number has too many digits |
| H_ERR_NOT_SYM | 3136 | Matrix is not symmetric |
| H_ERR_NUM_COLS | 3137 | Matrix is too big |
| H_ERR_SYNTAX | 3138 | Wrong structure of file |
| H_ERR_MISSING | 3139 | Lesser than 2 matrices |
| H_ERR_COOC_MEM | 3140 | Not enough memory |
| H_ERR_NO_FILE | 3141 | Can not read the file |
| H_ERR_FILE_WR | 3142 | Can not open file for writing |
| H_ERR_NUM_LUCOLS | 3143 | Too many lookup table colors |
| H_ERR_WNOLI | 3145 | Too many Hough points (lines) |
| H_ERR_DITS | 3146 | Target image has got wrong height (not big enough) |
| H_ERR_WINTM | 3147 | Wrong interpolation mode |
| H_ERR_THICK_NK | 3148 | Region not compact or not connected |
| H_ERR_WIND3 | 3170 | Wrong filter index for filter size 3 |
| H_ERR_WIND5 | 3171 | Wrong filter index for filter size 5 |
| H_ERR_WIND7 | 3172 | Wrong filter index for filter size 7 |
| H_ERR_WLAWSS | 3173 | Wrong filter size; only 3/5/7 |
| H_ERR_NE_NPTS | 3175 | Number of suitable pixels too small to reliably estimate the noise |
| H_ERR_WNEE | 3200 | Different number of entries/exits in HContCut |
| H_ERR_REF | 3201 | Reference to the underlying contour is missing |
| H_ERR_XLDWT | 3250 | Wrong XLD type |
| H_ERR_XLD_RPF | 3252 | Internal error: border point is set to FG |
| H_ERR_XLD_MCL | 3253 | Internal error: maximum contour length exceeded |
| H_ERR_XLD_MCN | 3254 | Internal error: maximum number of contours exceeded |
| H_ERR_XLD_CTS | 3255 | Contour too short for operator |
| H_ERR_XLD_CRD | 3256 | Regression parameters of contours already computed |
| H_ERR_XLD_CRND | 3257 | Regression parameters of contours not yet entered! Please compute them by calling regress_cont_xld |
| H_ERR_DBXC | 3258 | Data base: XLD object has been deleted |
| H_ERR_DBWXID | 3259 | Data base: object has no XLD-ID |

| Error Name | Code | Description |
|-----------------------------|------|---|
| H_ERR_XLD_WNP | 3260 | Internal error: wrong number of contour points allocated |
| H_ERR_XLD_CAND | 3261 | Contour attribute not defined |
| H_ERR_FIT_ELLIPSE | 3262 | Ellipse fitting failed |
| H_ERR_FIT_CIRCLE | 3263 | Circle fitting failed |
| H_ERR_FIT_CLIP | 3264 | All points classified as outliers (ClippingFactor too small or used points not similar to primitive) |
| H_ERR_FIT_QUADRANGLE | 3265 | Quadrangle fitting failed |
| H_ERR_INCOMPL_RECT | 3266 | No points found for at least one side of the rectangle |
| H_ERR_XLD_COI | 3267 | A contour point lies outside of the image |
| H_ERR_FIT_NOT_ENOUGH_POINTS | 3274 | Not enough valid points for fitting the model |
| H_ERR_NWF | 3275 | No ARC/INFO world file |
| H_ERR_NAIGF | 3276 | No ARC/INFO generate file |
| H_ERR_DXF_UEOF | 3278 | Unexpected end of file while reading DXF file |
| H_ERR_DXF_CRGC | 3279 | Cannot read DXF-group code from file |
| H_ERR_DXF_INAPP | 3280 | Inconsistent number of attributes per point in DXF file |
| H_ERR_DXF_INAPPN | 3281 | Inconsistent number of attributes and names in DXF file |
| H_ERR_DXF_INAPCN | 3282 | Inconsistent number of global attributes and names in DXF file |
| H_ERR_DXF_CRAPP | 3283 | Cannot read attributes from DXF file |
| H_ERR_DXF_CRAPC | 3284 | Cannot read global attributes from DXF file |
| H_ERR_DXF_CRAN | 3285 | Cannot read attribute names from DXF file |
| H_ERR_DXF_WPN | 3286 | Wrong generic parameter name |
| H_ERR_DXF_IEDT | 3289 | Internal DXF I/O error: Wrong data type |
| H_ERR_XLD_ISOL_POINT | 3290 | Isolated point while contour merging |
| H_ERR_NURBS_CCBF | 3291 | Constraints (MaxError/MaxDistance) cannot be fulfilled |
| H_ERR_NSEG | 3292 | No segment in contour |
| H_ERR_NO_ONE_P | 3293 | Only one or no point in template contour |
| H_ERR_SESF | 3300 | Syntax error in file for training |
| H_ERR_TMFE | 3301 | Maximum number of attributes per example exceeded |
| H_ERR_OPSPF | 3302 | Not possible to open file for training |
| H_ERR_TMSS | 3303 | Too many data sets for training |
| H_ERR_TMSAM | 3305 | Too many examples for one data set for training |
| H_ERR_TMCLS | 3306 | Too many classes |
| H_ERR_TMBOX | 3307 | Maximum number of cuboids exceeded |
| H_ERR_OPCF | 3308 | Not possible to open classifier's file |
| H_ERR_SCLA | 3309 | Error while saving the classifier |
| H_ERR_OPF | 3310 | Not possible to open protocol file |
| H_ERR_CLEX | 3311 | Classifier with this name is already existent |
| H_ERR_TMCLA | 3312 | Maximum number of classifiers exceeded |
| H_ERR_CNTRL | 3313 | Name of classifier is too long, ≥ 20 |
| H_ERR_CLNNF | 3314 | Classifier with this name is not existent |
| H_ERR_NCCLA | 3315 | Current classifier is not defined |
| H_ERR_CLASS2_ID | 3316 | Wrong id in classification file |
| H_ERR_CLASS2_VERS | 3317 | The version of the classifier is not supported |
| H_ERR_CLASS_NOSITEM | 3318 | Serialized item does not contain a valid classifier |
| H_ERR_TM_NO_CL | 3319 | Text model does not contain a classifier yet (use set_text_model_param) |
| H_ERR_KNN_CANNOT_ADD | 3320 | Adding new features is not possible, because the dataset has been normalized during training. Please create a new classifier and add all training data again or disable normalization during training |
| H_ERR_GMM_NOTRAINFILE | 3330 | Invalid file format for GMM training samples |
| H_ERR_GMM_WRTRAINVERS | 3331 | The version of the GMM training samples is not supported |
| H_ERR_GMM_WRSMPFORMAT | 3332 | Wrong training sample format |
| H_ERR_GMM_NOCLASSFILE | 3333 | Invalid file format for Gaussian Mixture Model (GMM) |
| H_ERR_GMM_WRCLASSVERS | 3334 | The version of the Gaussian Mixture Model (GMM) is not supported |
| H_ERR_GMM_TRAIN_UNKERR | 3335 | Internal error while training the GMM |

| Error Name | Code | Description |
|-------------------------------|------|--|
| H_ERR_GMM_TRAIN_COLLAPSED | 3336 | Singular covariance matrix |
| H_ERR_GMM_TRAIN_NOSAMPLE | 3337 | No samples for at least one class |
| H_ERR_GMM_TRAIN_FEWSAMPLES | 3338 | Too few samples for at least one class |
| H_ERR_GMM_NOTTRAINED | 3340 | GMM has not been trained yet |
| H_ERR_GMM_NOTRAINDATA | 3341 | No training samples stored in the classifier |
| H_ERR_GMM_NOSITEM | 3342 | Serialized item does not contain a valid Gaussian Mixture Model (GMM) |
| H_ERR_MLP_UNKOUTFUNC | 3350 | Unknown output function |
| H_ERR_MLP_NOTO1ENC | 3351 | Target vector not in 0-1 encoding |
| H_ERR_MLP_NOTRAINDATA | 3352 | No training samples stored in the classifier |
| H_ERR_MLP_NOTRAINFILE | 3353 | Invalid file format for MLP training samples |
| H_ERR_MLP_WRTRAINVERS | 3354 | The version of the MLP training samples is not supported |
| H_ERR_MLP_WRSMPFORMAT | 3355 | Wrong training sample format |
| H_ERR_MLP_NOCLASSIF | 3356 | MLP is not a classifier; use OutputFunction = 'softmax' in create_class_mlp |
| H_ERR_MLP_NOCLASSFILE | 3357 | Invalid file format for multilayer perceptron (MLP) |
| H_ERR_MLP_WRCLASSVERS | 3358 | The version of the multilayer perceptron (MLP) is not supported |
| H_ERR_WRNUMCHAN | 3359 | Wrong number of image channels |
| H_ERR_MLP_WRNUPPARAM | 3360 | Number of MLP parameters too large |
| H_ERR_MLP_NOSITEM | 3361 | Serialized item does not contain a valid multilayer perceptron (MLP) |
| H_ERR_LUT_WRNUMCHAN | 3370 | The number of image channels and the number of dimensions of the look-up table do not match |
| H_ERR_LUT_NRCHANLARGE | 3371 | A look-up table can be build only for a 2 or 3 channel classifier |
| H_ERR_LUT_CANNOTCREAT | 3372 | Cannot create a look-up table. Please choose a larger 'bit_depth' or select 'fast' for 'class_selection' |
| H_ERR_SVM_NOTRAINDATA | 3380 | No training samples stored in the classifier |
| H_ERR_SVM_NOTRAINFILE | 3381 | Invalid file format for SVM training samples |
| H_ERR_SVM_WRTRAINVERS | 3382 | The version of the SVM training samples is not supported |
| H_ERR_SVM_WRSMPFORMAT | 3383 | Wrong training sample format |
| H_ERR_SVM_NOCLASSFILE | 3384 | Invalid file format for support vector machine (SVM) |
| H_ERR_SVM_WRCLASSVERS | 3385 | The version of the support vector machine (SVM) is not supported |
| H_ERR_SVM_WRNRCCLASS | 3386 | Wrong number of classes |
| H_ERR_SVM_NU_TOO_BIG | 3387 | Nu was chosen too big |
| H_ERR_SVM_TRAIN_FAIL | 3388 | SVM training failed |
| H_ERR_SVM_DO_NOT_FIT | 3389 | Old SVM and new SVM do not match |
| H_ERR_SVM_NO_TRAIN_ADD | 3390 | SVM contains no trained support vectors |
| H_ERR_SVM_KERNELNOTRBF | 3391 | Kernel is not an RBF kernel |
| H_ERR_SVM_NO_TRAIND_FOR_CLASS | 3392 | Train data does not contain all classes |
| H_ERR_SVM_NOT_TRAINED | 3393 | SVM not trained |
| H_ERR_NOT_TRAINED | 3394 | Classifier not trained |
| H_ERR_SVM_NOSITEM | 3395 | Serialized item does not contain a valid support vector machine (SVM) |
| H_ERR_ROTNR | 3401 | Wrong rotation number |
| H_ERR_GOL | 3402 | Wrong letter for Golay element |
| H_ERR_BEZ | 3403 | Wrong reference point |
| H_ERR_ITER | 3404 | Wrong number of iterations |
| H_ERR_MOSYS | 3405 | Morphology: system error |
| H_ERR_ART | 3406 | Wrong type of boundary |
| H_ERR_OBBI | 3407 | Morphology: wrong number of input objects |
| H_ERR_OBBO | 3408 | Morphology: wrong number of output objects |
| H_ERR_PARI | 3409 | Morphology: wrong number of input control parameter |
| H_ERR_PARO | 3410 | Morphology: wrong number of output control parameter |
| H_ERR_SELC | 3411 | Morphology: structuring element is infinite |
| H_ERR_WRNSE | 3412 | Morphology: wrong name for structuring element |

| Error Name | Code | Description |
|----------------------------|------|---|
| H_ERR_WRRLN1 | 3500 | Wrong number of run length rows (chords): smaller than 0 |
| H_ERR_WRRLN2 | 3501 | Number of chords too big. Increase 'current_runlength_number' using set_system! |
| H_ERR_WRRLL | 3502 | Run length row with negative length |
| H_ERR_RLLTB | 3503 | Run length row \geq image height |
| H_ERR_RLLTS | 3504 | Run length row < 0 |
| H_ERR_RLCTB | 3505 | Run length column \geq image width |
| H_ERR_RLCTS | 3506 | Run length column < 0 |
| H_ERR_CHLTB | 3507 | For CHORD_TYPE: Number of row too big |
| H_ERR_CHLTS | 3508 | For CHORD_TYPE: Number of row too small |
| H_ERR_CHCTB | 3509 | For CHORD_TYPE: Number of column too big |
| H_ERR_MRLE | 3510 | Exceeding the maximum number of run lengths while automatic expansion |
| H_ERR_ICCOMPL | 3511 | Internal error: Region->compl neither true/false |
| H_ERR_RLEMAX | 3512 | Internal error: Region->max_num $<$ Region->num |
| H_ERR_WRRLN3 | 3513 | Internal error: number of chords too big for num_max |
| H_ERR_OPNOCOMPL | 3514 | Operator cannot be implemented for complemented regions; intersect the region with a finite region or set clip_region to true with set_system |
| H_ERR_WIMAW1 | 3520 | Image width must be positive |
| H_ERR_WIMAW2 | 3521 | Image width $>$ MAX_FORMAT |
| H_ERR_WIMAH1 | 3522 | Image height must be positive |
| H_ERR_WIMAH2 | 3523 | Image height $>$ MAX_FORMAT |
| H_ERR_WIMAW3 | 3524 | Image width ≤ 0 |
| H_ERR_WIMAH3 | 3525 | Image height ≤ 0 |
| H_ERR_TMS | 3550 | Too many segments |
| H_ERR_NO_INT8_IMAGE | 3551 | 'int8' images are available on 64 bit systems only |
| H_ERR_POINT_AT_INFINITY | 3600 | Point at infinity cannot be converted to a Euclidean point |
| H_ERR_ML_NO_COVARIANCE | 3601 | Covariance matrix could not be determined |
| H_ERR_RANSAC_PRNG | 3602 | RANSAC algorithm didn't find enough point correspondences |
| H_ERR_RANSAC_TOO_DIFFERENT | 3603 | RANSAC algorithm didn't find enough point correspondences |
| H_ERR_PTI_FALLBACK | 3604 | Internal diagnosis: fallback method had to be used |
| H_ERR_PTI_TRAFO_SING | 3605 | Projective transformation is singular |
| H_ERR_PTI_MOSAIC_UNDERDET | 3606 | Mosaic is under-determined |
| H_ERR_COV_NPD | 3607 | Input covariance matrix is not positive definite |
| H_ERR_TOO_MANY_POINTS | 3608 | Number of input points too large |
| H_ERR_INPC | 3620 | Inconsistent number of point correspondences |
| H_ERR_NOPA | 3621 | At least one image cannot be reached from the reference image |
| H_ERR_IINE | 3622 | The image with specified index does not exist |
| H_ERR_NOCM | 3623 | Matrix is not a camera matrix |
| H_ERR_SKNZ | 3624 | Skew is not zero |
| H_ERR_ILFL | 3625 | Illegal focal length |
| H_ERR_KANZ | 3626 | Distortion is not zero |
| H_ERR_VARA | 3627 | It is not possible to determine all parameters for variable camera parameters |
| H_ERR_LVDE | 3628 | No valid implementation selected |
| H_ERR_KPAR | 3629 | Kappa can only be determined with the gold-standard method |
| H_ERR_IMOD | 3630 | Conflicting number of images and projection mode |
| H_ERR_PNIC | 3631 | Error in projection: Point not in any cube map |
| H_ERR_NO_SOL | 3632 | No solution found |
| H_ERR_TINZ | 3633 | Tilt is not zero |
| H_ERR_ILMD | 3640 | Illegal combination of estimation method and parameters to be determined |
| H_ERR_NOFFTOPT | 3650 | Invalid file format for FFT optimization data |
| H_ERR_WRFFTOPTVERS | 3651 | The version of the FFT optimization data is not supported |
| H_ERR_WRHALCONVERS | 3652 | Optimization data was created with a different HALCON variant (Sequential HALCON / Parallel HALCON) |

| Error Name | Code | Description |
|----------------------------|------|---|
| H_ERR_OPTFAIL | 3653 | Storing of the optimization data failed |
| H_ERR_FFTOPT_NOSITEM | 3654 | Serialized item does not contain valid FFT optimization data |
| H_ERR_RDS_NSC | 3660 | No contours suitable for self-calibration found |
| H_ERR_RDS_NSS | 3661 | No stable solution found: please change the inlier threshold or select contours manually |
| H_ERR_RDS_ISS | 3662 | Unstable solution: please choose more or different contours |
| H_ERR_RDS_NEC | 3663 | Not enough contours for calibration: please select contours manually |
| H_ERR_INVLD_DISP_RANGE | 3690 | Disparity range exceeds the maximum permitted |
| H_ERR_EPIINIM | 3700 | Epipoles are within the image domain: no rectification possible |
| H_ERR_EPI_FOV | 3701 | Fields of view of both cameras do not intersect each other |
| H_ERR_EPI_RECT | 3702 | The stereo rectification is impossible |
| H_ERR_BI_WT_TARGET | 3710 | Wrong type of parameter target_thickness |
| H_ERR_BI_WT_THICKNESS | 3711 | Wrong type of parameter thickness_tolerance |
| H_ERR_BI_WT_POSITION | 3712 | Wrong type of parameter position_tolerance |
| H_ERR_BI_WT_SIGMA | 3713 | Wrong type of parameter sigma |
| H_ERR_BI_WV_SIGMA | 3714 | Wrong value of parameter sigma |
| H_ERR_BI_WT_THRESH | 3715 | Wrong type of parameter threshold |
| H_ERR_BI_WV_TARGET | 3716 | Wrong value of parameter target_thickness |
| H_ERR_BI_WV_THICKNESS | 3717 | Wrong value of parameter thickness_tolerance |
| H_ERR_BI_WV_POSITION | 3718 | Wrong value of parameter position_tolerance |
| H_ERR_BI_WV_THRESH | 3719 | Wrong value of parameter threshold |
| H_ERR_BI_WT_REFINE | 3720 | Wrong type of parameter refinement |
| H_ERR_BI_WV_REFINE | 3721 | Wrong value of parameter refinement |
| H_ERR_BI_WT_RESOL | 3722 | Wrong type of parameter resolution |
| H_ERR_BI_WV_RESOL | 3723 | Wrong value of parameter resolution |
| H_ERR_BI_WT_POLARITY | 3724 | Wrong type of parameter polarity |
| H_ERR_BI_WV_POLARITY | 3725 | Wrong value of parameter polarity |
| H_ERR_SOL_EMPTY_MODEL_LIST | 3751 | No sheet-of-light model available |
| H_ERR_SOL_WNIW | 3752 | Wrong input image size (width) |
| H_ERR_SOL_WNIH | 3753 | Wrong input image size (height) |
| H_ERR_SOL_WPROF_REG | 3754 | The bounding-box around the profile region does not fit the domain of definition of the input image |
| H_ERR_SOL_CAL_NONE | 3755 | Calibration extend not set |
| H_ERR_SOL_UNDEF_DISPARITY | 3756 | Undefined disparity image |
| H_ERR_SOL_UNDEF_DISPDOMAIN | 3757 | Undefined domain for disparity image |
| H_ERR_SOL_UNDEF_CAMPAR | 3758 | Undefined camera parameter |
| H_ERR_SOL_UNDEF_LPCS | 3759 | Undefined pose of the light plane |
| H_ERR_SOL_UNDEF_CCS | 3760 | Undefined pose of the camera coordinate system |
| H_ERR_SOL_UNDEF_CCS_2_LPCS | 3761 | Undefined transformation from the coordinate system of the camera to the coordinate system of the light plane |
| H_ERR_SOL_UNDEF_MOV_POSE | 3762 | Undefined movement pose for xyz calibration |
| H_ERR_SOL_WV_SCALE | 3763 | Wrong value of scale parameter |
| H_ERR_SOL_WV_PAR_NAME | 3764 | Wrong parameter name |
| H_ERR_SOL_WT_METHOD | 3765 | Wrong type of parameter method |
| H_ERR_SOL_WT_AMBIGUITY | 3766 | Wrong type of parameter ambiguity |
| H_ERR_SOL_WT_SCORE_TYPE | 3767 | Wrong type of parameter score |
| H_ERR_SOL_WT_CALIBRATION | 3768 | Wrong type of parameter calibration |
| H_ERR_SOL_WT_NUM_PROF | 3769 | Wrong type of parameter number_profiles |
| H_ERR_SOL_WT_CAM_PAR | 3770 | Wrong type of element in parameter camera_parameter |
| H_ERR_SOL_WT_PAR_POSE | 3771 | Wrong type of element in pose |
| H_ERR_SOL_WV_METHOD | 3772 | Wrong value of parameter method |
| H_ERR_SOL_WT_THRES | 3773 | Wrong type of parameter min_gray |
| H_ERR_SOL_WV_AMBIGUITY | 3774 | Wrong value of parameter ambiguity |
| H_ERR_SOL_WV_SCORE_TYPE | 3775 | Wrong value of parameter score_type |
| H_ERR_SOL_WV_CALIBRATION | 3776 | Wrong value of parameter calibration |
| H_ERR_SOL_WV_NUM_PROF | 3777 | Wrong value of parameter number_profiles |

| Error Name | Code | Description |
|--------------------------------|------|---|
| H_ERR_SOL_WV_CAMERA_TYPE | 3778 | Wrong type of camera |
| H_ERR_SOL_WN_CAM_PAR | 3779 | Wrong number of values of parameter camera_parameter |
| H_ERR_SOL_WN_POSE | 3780 | Wrong number of values of parameter pose |
| H_ERR_SOL_NO_TARGET_FOUND | 3781 | Calibration target not found |
| H_ERR_SOL_NO_VALID_SOL | 3782 | The calibration algorithm failed to find a valid solution |
| H_ERR_SOL_WT_CALIB_OBJECT | 3783 | Wrong type of parameter calibration_object |
| H_ERR_SOL_INVALID_CALIB_OBJECT | 3784 | Invalid calibration object |
| H_ERR_SOL_NO_CALIB_OBJECT_SET | 3785 | No calibration object set |
| H_ERR_SOL_WR_FILE_FORMAT | 3786 | Invalid file format for sheet-of-light model |
| H_ERR_SOL_WR_FILE_VERS | 3787 | The version of the sheet-of-light model is not supported |
| H_ERR_SOL_CAMPAR_UNSUPPORTED | 3788 | Camera type not supported by calibrate_sheet_of_light_model |
| H_ERR_SOL_PAR_CALIB | 3790 | Parameter does not match the set 'calibration' |
| H_ERR_SOL_WGV_DISP | 3791 | The gray values of the disparity image, which specify rows in the camera image, do not fit the height of the camera |
| H_ERR_TI_WRONGMODEL | 3800 | Texture inspection model has the wrong type |
| H_ERR_TI_NOTTRAINED | 3801 | Texture inspection model is not trained |
| H_ERR_TI_NOTRAINDATA | 3802 | Texture inspection model has no training data |
| H_ERR_TI_NOTRAINFILE | 3803 | Invalid file format for a texture inspection model |
| H_ERR_TI_WRTRAINVERS | 3804 | The version of the texture inspection model is not supported |
| H_ERR_TI_WRSMPFORMAT | 3805 | Invalid file format for the training samples |
| H_ERR_TI_WRSMPVERS | 3806 | The version of the training sample file is not supported |
| H_ERR_TI_WRIMGSIZE | 3807 | At least one of the images within the texture inspection model is too small |
| H_ERR_TI_WRSMPTEXMODEL | 3808 | The read samples do not match the current texture model |
| H_ERR_NOT_ENOUGH_IMAGES | 3809 | The texture model does not contain any images |
| H_ERR_SING | 3850 | The light source positions are linearly dependent |
| H_ERR_FEWIM | 3851 | No sufficient image indication |
| H_ERR_ZBR_NOS | 3852 | Internal error: Function has equal signs in HZBrent |
| H_ERR_DIMK | 3900 | Kalman: Dimension n,m or p has got a undefined value |
| H_ERR_NOFILE | 3901 | Kalman: File does not exist |
| H_ERR_FF1 | 3902 | Kalman: Error in file (row of dimension) |
| H_ERR_FF2 | 3903 | Kalman: Error in file (row of marking) |
| H_ERR_FF3 | 3904 | Kalman: Error in file (value is no float) |
| H_ERR_NO_A | 3905 | Kalman: Matrix A is missing in file |
| H_ERR_NO_C | 3906 | Kalman: Matrix C is missing in file |
| H_ERR_NO_Q | 3907 | Kalman: Matrix Q is missing in file |
| H_ERR_NO_R | 3908 | Kalman: Matrix R is missing in file |
| H_ERR_NO_GU | 3909 | Kalman: G or u is missing in file |
| H_ERR_NOTSYMM | 3910 | Kalman: Covariant matrix is not symmetric |
| H_ERR_SINGU | 3911 | Kalman: Equation system is singular |
| H_ERR_SLM_NOT_PERSISTENT | 3950 | Feature or operation available only in 'persistent' mode |
| H_ERR_SLM_MSW_TOO_LARGE | 3951 | 'min_stripe_width' is too large for the selected 'pattern_width' and/or 'pattern_height' |
| H_ERR_SLM_SSW_TOO_LARGE | 3952 | 'single_stripe_width' is too large for the selected 'pattern_width' and/or 'pattern_height' |
| H_ERR_SLM_MSW_GT_SSW | 3953 | 'min_stripe_width' has to be smaller or equal 'single_stripe_width' |
| H_ERR_SLM_SSW_LT_MSW | 3954 | 'single_stripe_width' is too small for the selected 'min_stripe_width' |
| H_ERR_SLM_NOT_PREP | 3955 | The structured light model can only be decoded after calling 'gen_structured_light_pattern' |
| H_ERR_SLM_NO_OBJS | 3956 | The structured light model does not contain the queried object |
| H_ERR_SLM_WRVERS | 3957 | The version of the structured light model is not supported |
| H_ERR_SLM_WRFIL | 3958 | Invalid file format for a structured light model |
| H_ERR_SLM_WRONGPATTERN | 3959 | Parameter does not match the set 'pattern_type' |
| H_ERR_SLM_NOT_DECODED | 3960 | 'defect_image' can only be computed after calling 'decode_structured_light_pattern' |

| Error Name | Code | Description |
|-----------------------------------|------|---|
| H_ERR_SLM_WRONGMODEL | 3961 | The structured light model has the wrong type |
| H_ERR_SLM_WNUMCAMS | 3962 | The camera setup model has to contain two sets of camera parameters |
| H_ERR_SLM_WPATTSIZE | 3963 | 'pattern_width' and 'pattern_height' do not match the projector parameters in the set 'camera_setup_model' |
| H_ERR_SLM_WRONGCTYPE | 3964 | Camera type not supported by the structured light model |
| H_ERR_SLM_WRONGPTYPE | 3965 | Projector type not supported by the structured light model |
| H_ERR_SLM_NO_CSM | 3966 | The structured light model does not contain a camera setup model |
| H_ERR_SLM_NO_VERT | 3967 | 'pattern_orientation' does not contain vertical orientation |
| H_ERR_SLM_NOT_DEC_REC | 3968 | 'reconstruct_surface_structured_light' can only be called after 'decode_structured_light_pattern' |
| H_ERR_SLM_WCAMSIZE | 3969 | Size of correspondence image does not match the camera parameters in the set 'camera_setup_model' |
| H_ERR_DBOIT | 4050 | Image data management: object is an object tuple |
| H_ERR_DBOC | 4051 | Image data management: object has been deleted already |
| H_ERR_DBOID | 4052 | Image data management: wrong object-ID |
| H_ERR_DBTC | 4053 | Image data management: object tuple has been deleted already |
| H_ERR_DBTID | 4054 | Image data management: wrong object tuple-ID |
| H_ERR_DBTIO | 4055 | Image data management: object tuple is an object |
| H_ERR_DBIDNULL | 4056 | Image data management: object-ID is NULL (0) |
| H_ERR_WDBID | 4057 | Image data management: object-ID outside the valid range |
| H_ERR_DBIC | 4058 | Image data management: access to deleted image |
| H_ERR_DBIID | 4059 | Image data management: access to image with wrong key |
| H_ERR_DBRG | 4060 | Image data management: access to deleted region |
| H_ERR_DBRID | 4061 | Image data management: access to region with wrong key |
| H_ERR_WCHAN | 4062 | Image data management: wrong value for image channel |
| H_ERR_DBITL | 4063 | Image data management: index too big |
| H_ERR_DBIUNDEF | 4064 | Image data management: index not defined |
| H_ERR_NO_OPENCL | 4100 | No OpenCL available |
| H_ERR_OPENCL_ERROR | 4101 | OpenCL Error occurred |
| H_ERR_NO_COMPUTE_DEVICES | 4102 | No compute device available |
| H_ERR_NO_DEVICE_IMPL | 4103 | No device implementation for this parameter |
| H_ERR_OUT_OF_DEVICE_MEM | 4104 | Out of compute device memory |
| H_ERR_INVALID_SHAPE | 4105 | Invalid work group shape |
| H_ERR_INVALID_DEVICE | 4106 | Invalid compute device |
| H_ERR_CUDA_ERROR | 4200 | CUDA Error occurred |
| H_ERR_CUDNN_ERROR | 4201 | cuDNN Error occurred |
| H_ERR_CUBLAS_ERROR | 4202 | cuBLAS Error occurred |
| H_ERR_BATCH_SIZE_NOT_SUPPORTED | 4203 | Setting the batch size on CPUs is not supported. For more information, please read the documentation of the parameter |
| H_ERR_CUDA_NOT_AVAILABLE | 4204 | CUDA implementations are not available |
| H_ERR_CUDNN_UNSUPPORTED_VERSION | 4205 | Unsupported version of cuDNN |
| H_ERR_CUDNN_FEATURE_NOT_SUPPORTED | 4206 | Current configuration requests a feature not supported by cuDNN. Use different input size and/or the batch size! |
| H_ERR_CUDA_DRIVER_VERSION | 4207 | Your graphics driver does not support the required CUDA version. Please update your graphics driver! |
| H_ERR_TRAINING_UNSUPPORTED | 4301 | Training is unsupported with the selected runtime. |
| H_ERR_CPU_INFERENCE_NOT_AVAILABLE | 4302 | CPU based inference is not supported on this platform |
| H_ERR_DNNL_ERROR | 4303 | Error occurred in DNNL library |
| H_ERR_HAI2_ERROR | 4320 | Error occurred in an AI Accelerator Interface |
| H_ERR_HAI2_INVALID_PARAM | 4321 | Invalid parameter for AI Accelerator Interface |
| H_ERR_ACL_ERROR | 4400 | Error occurred in ACL library |
| H_ERR_VISUALIZATION | 4500 | Internal visualization error |
| H_ERR_COLOR_TYPE_UNEXP | 4501 | Unexpected color type |
| H_ERR_NUM_COLOR_EXCEEDED | 4502 | Number of color settings exceeded |
| H_ERR_WSCN | 5100 | Wrong (logical) window number |

| Error Name | Code | Description |
|-------------|------|---|
| H_ERR_DSCO | 5101 | Error while opening the window |
| H_ERR_WWC | 5102 | Wrong window coordinates |
| H_ERR_NWA | 5103 | It is not possible to open another window |
| H_ERR_DNA | 5104 | Device or operator not available |
| H_ERR_UCOL | 5105 | Unknown color |
| H_ERR_NWO | 5106 | No window has been opened for desired action |
| H_ERR_WFM | 5107 | Wrong filling mode for regions (fill or margin) |
| H_ERR_WGV | 5108 | Wrong gray value (0..255) |
| H_ERR_WPV | 5109 | Wrong pixel value (use value of get_pixel(P) only) |
| H_ERR_WLW | 5110 | Wrong line width (see: query_line_width(Min,Max)) |
| H_ERR_WCUR | 5111 | Wrong name of cursor |
| H_ERR_WLUT | 5112 | Wrong color table (see: query_lut(Name)) |
| H_ERR_WDM | 5113 | Wrong representation mode (see: query_insert(Mode)) |
| H_ERR_WRCO | 5114 | Wrong representation color (see: query_color(List)) |
| H_ERR_WRDM | 5115 | Wrong dither matrix (binary image representation) |
| H_ERR_WRIT | 5116 | Wrong image transformation (name or image size) |
| H_ERR_IPIT | 5117 | Unsuitable image type for image transformation |
| H_ERR_WRZS | 5118 | Wrong zooming factor for image transformation |
| H_ERR_WRDS | 5119 | Wrong representation mode |
| H_ERR_WRDV | 5120 | Wrong code of device |
| H_ERR_WWINF | 5121 | Wrong number for father window |
| H_ERR_WDEXT | 5122 | Wrong window size |
| H_ERR_WWT | 5123 | Wrong window type |
| H_ERR_WND | 5124 | No current window has been set |
| H_ERR_WRGB | 5125 | Wrong color combination or range (RGB) |
| H_ERR_WPNS | 5126 | Wrong number of pixels set |
| H_ERR_WCM | 5127 | Wrong value for comprise (object or image) |
| H_ERR_FNA | 5128 | set_fix with 1/4 image levels and static not valid |
| H_ERR_LNFS | 5129 | set_lut not valid in child windows |
| H_ERR_LOFL | 5130 | Number of concurrent used color tables is too big |
| H_ERR_WIDT | 5131 | Wrong device for window dump |
| H_ERR_WWDS | 5132 | Wrong window size for window dump |
| H_ERR_NDVS | 5133 | System variable DISPLAY (setenv) not defined |
| H_ERR_WBW | 5134 | Wrong thickness for window margin |
| H_ERR_WDVS | 5135 | System variable DISPLAY has been set wrong (<host>:0.0) |
| H_ERR_TMF | 5136 | Too many fonts loaded |
| H_ERR_WFN | 5137 | Wrong font name |
| H_ERR_WCP | 5138 | No valid cursor position |
| H_ERR_NTW | 5139 | Window is not a textual window |
| H_ERR_NPW | 5140 | Window is not a image window |
| H_ERR_STL | 5141 | String too long or too high |
| H_ERR_NSS | 5142 | Too little space in the window rightwards |
| H_ERR_NMS | 5143 | Window is not suitable for the mouse |
| H_ERR_DWNA | 5144 | Here Windows on a equal machine is permitted only |
| H_ERR_WOM | 5145 | Wrong mode while opening a window |
| H_ERR_WWM | 5146 | Wrong window mode for operation |
| H_ERR_LUTF | 5147 | Operation not possible with fixed pixel |
| H_ERR_LUTN8 | 5148 | Color tables for 8 image levels only |
| H_ERR_WTCM | 5149 | Wrong mode for pseudo real colors |
| H_ERR_WIFTL | 5150 | Wrong pixel value for LUT |
| H_ERR_WSOI | 5151 | Wrong image size for pseudo real colors |
| H_ERR_HRLUT | 5152 | Error in procedure HRLUT |
| H_ERR_WPFSL | 5153 | Wrong number of entries in color table for set_lut |
| H_ERR_WPVS | 5154 | Wrong values for image area |
| H_ERR_WLPN | 5155 | Wrong line pattern |
| H_ERR_WLPL | 5156 | Wrong number of parameters for line pattern |

| Error Name | Code | Description |
|-----------------------------|------|---|
| H_ERR_WNOC | 5157 | Wrong number of colors |
| H_ERR_WPST | 5158 | Wrong value for mode of area creation (0,1,2) |
| H_ERR_SWNA | 5159 | Spy window is not set (set_spy) |
| H_ERR_NSFO | 5160 | No file for spy has been set (set_spy) |
| H_ERR_WSPN | 5161 | Wrong parameter output depth (set_spy) |
| H_ERR_WIFFD | 5162 | Wrong window size for window dump |
| H_ERR_WLUTF | 5163 | Wrong color table: wrong file name or query_lut() |
| H_ERR_WLUTE | 5164 | Wrong color table: empty string? |
| H_ERR_WLUTD | 5165 | Using this hardware set_lut('default') is allowed only |
| H_ERR_CNDP | 5166 | Error while calling online help |
| H_ERR_LNPR | 5167 | Row can not be projected |
| H_ERR_NFSC | 5168 | Operation is unsuitable using a computer with fixed color table |
| H_ERR_NACD | 5169 | Computer represents gray scales only (no colors) |
| H_ERR_LUTO | 5170 | LUT of this display is full |
| H_ERR_WCC | 5171 | Internal error: wrong color code |
| H_ERR_WWATTRT | 5172 | Wrong type for window attribute |
| H_ERR_WWATTRN | 5173 | Wrong name for window attribute |
| H_ERR_WRSPART | 5174 | Negative height of area (or 0) |
| H_ERR_WCSPART | 5175 | Negative width of area (or 0) |
| H_ERR_WNCV | 5176 | Window not completely visible |
| H_ERR_FONT_NA | 5177 | Font not allowed for this operation |
| H_ERR_WDIFFTH | 5178 | Operation not possible (window was created in different thread) |
| H_ERR_DEPTH_NOT_STORED | 5179 | Depth was not stored with window |
| H_ERR_CHA3 | 5180 | Internal error: only RGB-Mode |
| H_ERR_NMWA | 5181 | No more (image-)windows available |
| H_ERR_INDEX_NOT_STORED | 5182 | Object index was not stored with window |
| H_ERR_PRIM_NO_POINTS | 5183 | Operator does not support primitives without point coordinates |
| H_ERR_REMOTE_DESKTOP_SIZE | 5184 | Maximum image size for Windows Remote Desktop exceeded |
| H_ERR_NOGL | 5185 | No OpenGL support available |
| H_ERR_NODEPTH | 5186 | No depth information available |
| H_ERR_OGL_ERROR | 5187 | OpenGL error occurred |
| H_ERR_UNSUPPORTED_FBO | 5188 | Required framebuffer object is unsupported |
| H_ERR_OGL_HSR_NOT_SUPPORTED | 5189 | OpenGL accelerated hidden surface removal not supported on this machine |
| H_ERR_WP_IWP | 5190 | Invalid window parameter |
| H_ERR_WP_IWPV | 5191 | Invalid value for window parameter |
| H_ERR_UMOD | 5192 | Unknown mode |
| H_ERR_ATTIMG | 5193 | No image has been previously attached to window |
| H_ERR_OBJ_ATTACHED | 5194 | The drawing object has already been attached to another window |
| H_ERR_NVG_WM | 5195 | Invalid value of navigation mode |
| H_ERR_FINTERN | 5196 | Internal file error |
| H_ERR_FS | 5197 | Error while file synchronization |
| H_ERR_FISR | 5198 | Insufficient rights on file |
| H_ERR_BFD | 5199 | Bad file descriptor |
| H_ERR_FNF | 5200 | File not found |
| H_ERR_DWI | 5201 | Error while writing image data (sufficient memory?) |
| H_ERR_DWID | 5202 | Error while writing image descriptor (sufficient memory?) |
| H_ERR_DRI1 | 5203 | Error while reading image data (format of image too small?) |
| H_ERR_DRI2 | 5204 | Error while reading image data (format of image too big?) |
| H_ERR_DRID1 | 5205 | Error while reading image descriptor: file too small |
| H_ERR_DIMMAT | 5206 | Image matrices are different |
| H_ERR_HNF | 5207 | Help file not found (setenv HALCONROOT <HALCON-Homedirectory>) |
| H_ERR_XNF | 5208 | Help index not found (setenv HALCONROOT <HALCON-Homedirectory>) |

| Error Name | Code | Description |
|----------------------|------|---|
| H_ERR_CNCSI | 5209 | File <standard_input> can not be closed |
| H_ERR_CNCSO | 5210 | <standard_output/error> can not be closed |
| H_ERR_CNCF | 5211 | File can not be closed |
| H_ERR_EDWF | 5212 | Error while writing to file |
| H_ERR_NFA | 5213 | Exceeding of maximum number of files |
| H_ERR_WFIN | 5214 | Wrong file name |
| H_ERR_CNOF | 5215 | Error while opening the file |
| H_ERR_WFMO | 5216 | Wrong file mode |
| H_ERR_WPTY | 5217 | Wrong type for pixel (e.g. byte) |
| H_ERR_WIW | 5218 | Wrong image width (too big?) |
| H_ERR_WIH | 5219 | Wrong image height (too big?) |
| H_ERR_FTS1 | 5220 | File already exhausted before reading an image |
| H_ERR_FTS2 | 5221 | File exhausted before terminating the image |
| H_ERR_WDPI | 5222 | Wrong value for resolution (dpi) |
| H_ERR_WNOW | 5223 | Wrong output image size (width) |
| H_ERR_WNOH | 5224 | Wrong output image size (height) |
| H_ERR_WNFP | 5225 | Wrong number of parameter values: format description |
| H_ERR_WPNA | 5226 | Wrong parameter name for operator |
| H_ERR_WSNA | 5227 | Wrong slot name for parameter |
| H_ERR_NPCF | 5228 | Operator class is missing in help file |
| H_ERR_WHIF | 5229 | Wrong or inconsistent help/* .idx or help/* .sta |
| H_ERR_HINF | 5230 | File help/* .idx not found (setenv HALCONROOT <HALCON-Homedirectory>) |
| H_ERR_HSNF | 5231 | File help/* .sta not found (setenv HALCONROOT <HALCON-Homedirectory>) |
| H_ERR_ICSF | 5232 | Inconsistent file help/* .sta |
| H_ERR_EFNF | 5233 | No explication file (.exp) found |
| H_ERR_NFWKEF | 5234 | No file found in known graphic format |
| H_ERR_WIFT | 5235 | Wrong graphic format |
| H_ERR_ICNF | 5236 | Inconsistent file halcon.num |
| H_ERR_WTIFF | 5237 | File not a TIFF file |
| H_ERR_WFF | 5238 | Wrong file format |
| H_ERR_NOGPPROC | 5239 | gnuplot could not be started |
| H_ERR_NOGPPFILE | 5240 | Output file for gnuplot could not be opened |
| H_ERR_NOGPOUT | 5241 | Not a valid gnuplot output stream |
| H_ERR_NOPNM | 5242 | No PNM format |
| H_ERR_ICODB | 5243 | Inconsistent or old help file (\$HALCONROOT/help) |
| H_ERR_INVAL_FILE_ENC | 5244 | Invalid text file encoding |
| H_ERR_FNO | 5245 | File not open |
| H_ERR_NO_FILES | 5246 | No files in use so far (none opened) |
| H_ERR_NORFILE | 5247 | Invalid file format for regions |
| H_ERR_RDTB | 5248 | Error while reading region data: Format of region too big |
| H_ERR_BINFILE_ENC | 5249 | Setting the encoding is not supported for binary files |
| H_ERR_EDRF | 5250 | Error while reading from file |
| H_ERR_SNO | 5251 | Serial port not open |
| H_ERR_NSA | 5252 | No serial port available |
| H_ERR_CNOS | 5253 | Could not open serial port |
| H_ERR_CNCS | 5254 | Could not close serial port |
| H_ERR_CNGSA | 5255 | Could not get serial port attributes |
| H_ERR_CNSSA | 5256 | Could not set serial port attributes |
| H_ERR_WRSBR | 5257 | Wrong baud rate for serial connection |
| H_ERR_WRSDB | 5258 | Wrong number of data bits for serial connection |
| H_ERR_WRSFC | 5259 | Wrong flow control for serial connection |
| H_ERR_CNFS | 5260 | Could not flush serial port |
| H_ERR_EDWS | 5261 | Error during write to serial port |
| H_ERR_EDRS | 5262 | Error during read from serial port |

| Error Name | Code | Description |
|----------------------|------|--|
| H_ERR_REG_NOSITEM | 5270 | Serialized item does not contain valid regions |
| H_ERR_REG_WRVERS | 5271 | The version of the regions is not supported |
| H_ERR_IMG_NOSITEM | 5272 | Serialized item does not contain valid images |
| H_ERR_IMG_WRVERS | 5273 | The version of the images is not supported |
| H_ERR_XLD_NOSITEM | 5274 | Serialized item does not contain valid XLD objects |
| H_ERR_XLD_WRVERS | 5275 | The version of the XLD objects is not supported |
| H_ERR_OBJ_NOSITEM | 5276 | Serialized item does not contain valid objects |
| H_ERR_OBJ_WRVERS | 5277 | The version of the objects is not supported |
| H_ERR_OBJ_UNEXPECTED | 5279 | Unexpected object detected |
| H_ERR_FNOTF | 5280 | File has not been opened in text format |
| H_ERR_FNOBF | 5281 | File has not been opened in binary file format |
| H_ERR_DIRCR | 5282 | Cannot create directory |
| H_ERR_DIRRM | 5283 | Cannot remove directory |
| H_ERR_GETCWD | 5284 | Cannot determine current directory |
| H_ERR_SETCWD | 5285 | Cannot set current directory |
| H_ERR_XINIT | 5286 | Missing call to XInitThreads: multithreading support for X11 required |
| H_ERR_NFS | 5300 | No image acquisition device opened |
| H_ERR_FGWC | 5301 | Image acquisition: wrong color depth |
| H_ERR_FGWD | 5302 | Image acquisition: wrong device |
| H_ERR_FGVF | 5303 | Image acquisition: determination of video format not possible |
| H_ERR_FGNV | 5304 | Image acquisition: no video signal |
| H_ERR_UFG | 5305 | Unknown image acquisition device |
| H_ERR_FGF | 5306 | Image acquisition: failed grabbing of an image |
| H_ERR_FGWR | 5307 | Image acquisition: wrong resolution chosen |
| H_ERR_FGWP | 5308 | Image acquisition: wrong image part chosen |
| H_ERR_FGWPR | 5309 | Image acquisition: wrong pixel ratio chosen |
| H_ERR_FGWH | 5310 | Image acquisition: handle not valid |
| H_ERR_FGCL | 5311 | Image acquisition: instance not valid (already closed?) |
| H_ERR_FGNI | 5312 | Image acquisition: device cannot be initialized |
| H_ERR_FGET | 5313 | Image acquisition: external triggering not supported |
| H_ERR_FGLI | 5314 | Image acquisition: wrong camera input line (multiplex) |
| H_ERR_FGCS | 5315 | Image acquisition: wrong color space |
| H_ERR_FGPT | 5316 | Image acquisition: wrong port |
| H_ERR_FGCT | 5317 | Image acquisition: wrong camera type |
| H_ERR_FGTM | 5318 | Image acquisition: maximum number of acquisition device classes exceeded |
| H_ERR_FGDV | 5319 | Image acquisition: device busy |
| H_ERR_FGASYNC | 5320 | Image acquisition: asynchronous grab not supported |
| H_ERR_FGPARAM | 5321 | Image acquisition: unsupported parameter |
| H_ERR_FGTIMEOUT | 5322 | Image acquisition: timeout |
| H_ERR_FGGAIN | 5323 | Image acquisition: invalid gain |
| H_ERR_FGFIELD | 5324 | Image acquisition: invalid field |
| H_ERR_FGPART | 5325 | Image acquisition: invalid parameter type |
| H_ERR_FGPARV | 5326 | Image acquisition: invalid parameter value |
| H_ERR_FGFNS | 5327 | Image acquisition: function not supported |
| H_ERR_FGIVERS | 5328 | Image acquisition: incompatible interface version |
| H_ERR_FGSETPAR | 5329 | Image acquisition: could not set parameter value |
| H_ERR_FGGETPAR | 5330 | Image acquisition: could not query parameter setting |
| H_ERR_FGPARNA | 5331 | Image acquisition: parameter not available in current configuration |
| H_ERR_FGCLOSE | 5332 | Image acquisition: device could not be closed properly |
| H_ERR_FGCAMFILE | 5333 | Image acquisition: camera configuration file could not be opened |
| H_ERR_FGCALLBACK | 5334 | Image acquisition: callback type not supported |
| H_ERR_FGDEVLOST | 5335 | Image acquisition: device lost |
| H_ERR_FGABORTED | 5336 | Image acquisition: aborted |

| Error Name | Code | Description |
|--------------------------------------|------|---|
| H_ERR_IOTIMEOUT | 5350 | IO: timeout |
| H_ERR_IOIVERS | 5351 | IO: incompatible interface version |
| H_ERR_IOWH | 5352 | IO: handle not valid |
| H_ERR_IODBUSY | 5353 | IO: device busy |
| H_ERR_IOIAR | 5354 | IO: insufficient user rights |
| H_ERR_IONF | 5355 | IO: device or channel not found |
| H_ERR_IOPART | 5356 | IO: invalid parameter type |
| H_ERR_IOPARV | 5357 | IO: invalid parameter value |
| H_ERR_IOPARNUM | 5358 | IO: invalid number of parameters |
| H_ERR_IOPARAM | 5359 | IO: unsupported parameter |
| H_ERR_IOPARNA | 5360 | IO: parameter not available in current configuration |
| H_ERR_IOFNS | 5361 | IO: function not supported |
| H_ERR_IOME | 5362 | IO: maximum number of IO devices or channels exceeded |
| H_ERR_IODNA | 5363 | IO: driver of IO device not available |
| H_ERR_IOABORTED | 5364 | IO: aborted |
| H_ERR_IODATT | 5365 | IO: invalid data type |
| H_ERR_IODEVLOST | 5366 | IO: device lost |
| H_ERR_IOSETPAR | 5367 | IO: could not set parameter value |
| H_ERR_IOGETPAR | 5368 | IO: could not query parameter value |
| H_ERR_IOCLOSE | 5369 | IO: device could not be closed properly |
| H_ERR_JXR_UNSUPPORTED_FORMAT | 5400 | Image type is not supported |
| H_ERR_JXR_INVALID_PIXEL_FORMAT | 5401 | Invalid pixel format |
| H_ERR_JXR_INTERNAL_ERROR | 5402 | Internal JPEG-XR error |
| H_ERR_JXR_FORMAT_SYNTAX_ERROR | 5403 | Invalid format string |
| H_ERR_JXR_TOO_MANY_CHANNELS | 5404 | Maximum number of channels exceeded |
| H_ERR_JXR_EC_ERROR | 5405 | Unspecified error in JPEG-XR library |
| H_ERR_JXR_EC_BADMAGIC | 5406 | Bad magic number in JPEG-XR library |
| H_ERR_JXR_EC_FEATURE_NOT_IMPLEMENTED | 5407 | Feature not implemented in JPEG-XR library |
| H_ERR_JXR_EC_IO | 5408 | File read/write error in JPEG-XR library |
| H_ERR_JXR_EC_BADFORMAT | 5409 | Invalid file format in JPEG-XR library |
| H_ERR_LIB_FILE_CLOSE | 5500 | Error while closing the image file |
| H_ERR_LIB_FILE_OPEN | 5501 | Error while opening the image file |
| H_ERR_LIB_UNEXPECTED_EOF | 5502 | Premature end of the image file |
| H_ERR_IDTL | 5503 | Image dimensions too large for this file format |
| H_ERR_ITLHV | 5504 | Image too large for this HALCON version |
| H_ERR_TMIO | 5505 | Too many iconic objects for this file format |
| H_ERR_FILE_FORMAT_UNSUPPORTED | 5506 | File format is unsupported |
| H_ERR_INCONSISTENT_DIMENSIONS | 5507 | All channels must have equal dimensions |
| H_ERR_PCX_NO_PCX_FILE | 5510 | File is no PCX-File |
| H_ERR_PCX_UNKNOWN_ENCODING | 5511 | PCX: unknown encoding |
| H_ERR_PCX_MORE_THAN_4_PLANES | 5512 | PCX: More than 4 image plains |
| H_ERR_PCX_COLORMAP_SIGNATURE | 5513 | PCX: Wrong magic in color table |
| H_ERR_PCX_REPEAT_COUNT_SPANS | 5514 | PCX: Wrong number of bytes in span |
| H_ERR_PCX_TOO_MUCH_BITS_PIXEL | 5515 | PCX: Wrong number of bits/pixels |
| H_ERR_PCX_PACKED_PIXELS | 5516 | PCX: Wrong number of plains |
| H_ERR_GIF_NO_GIF_PICTURE | 5520 | File is no GIF-File |
| H_ERR_GIF_BAD_VERSION | 5521 | GIF: Wrong version (not 87a/89a) |
| H_ERR_GIF_SCREEN_DESCRIPTOR | 5522 | GIF: Wrong descriptor |
| H_ERR_GIF_COLORMAP | 5523 | GIF: Wrong color table |
| H_ERR_GIF_READ_ERROR_EOF | 5524 | GIF: Premature end of file |
| H_ERR_GIF_NOT_ENOUGH_IMAGES | 5525 | GIF: Wrong number of images ',' |
| H_ERR_GIF_ERROR_ON_EXTENSION | 5526 | GIF: Wrong image extension '!' |
| H_ERR_GIF_LEFT_TOP_WIDTH | 5527 | GIF: Wrong left top width |
| H_ERR_GIF_CIRCULAR_TABL_ENTRY | 5528 | GIF: Cyclic index of table |
| H_ERR_GIF_BAD_IMAGE_DATA | 5529 | GIF: Wrong image data |
| H_ERR_SUN_RASTERFILE_TYPE | 5530 | File is no Sun-Raster-File |

| Error Name | Code | Description |
|----------------------------------|------|---|
| H_ERR_SUN_RASTERFILE_HEADER | 5531 | SUN-Raster: Wrong header |
| H_ERR_SUN_COLS | 5532 | SUN-Raster: Wrong image width |
| H_ERR_SUN_ROWS | 5533 | SUN-Raster: Wrong image height |
| H_ERR_SUN_COLORMAP | 5534 | SUN-Raster: Wrong color map |
| H_ERR_SUN_RASTERFILE_IMAGE | 5535 | SUN-Raster: Wrong image data |
| H_ERR_SUN_IMPOSSIBLE_DATA | 5536 | SUN-Raster: Wrong type of pixel |
| H_ERR_XWD_IMPOSSIBLE_DATA | 5540 | XWD: Wrong type of pixel |
| H_ERR_XWD_VISUAL_CLASS | 5541 | XWD: Wrong visual class |
| H_ERR_XWD_X10_HEADER | 5542 | XWD: Wrong X10 header |
| H_ERR_XWD_X11_HEADER | 5543 | XWD: Wrong X11 header |
| H_ERR_XWD_X10_COLORMAP | 5544 | XWD: Wrong X10 colormap |
| H_ERR_XWD_X11_COLORMAP | 5545 | XWD: Wrong X11 colormap |
| H_ERR_XWD_X11_PIXMAP | 5546 | XWD: Wrong pixmap |
| H_ERR_XWD_UNKNOWN_VERSION | 5547 | XWD: unknown version |
| H_ERR_XWD_READING_IMAGE | 5548 | XWD: Error while reading an image |
| H_ERR_TIF_BAD_INPUTDATA | 5550 | TIFF: Error while reading a file |
| H_ERR_TIF_COLORMAP | 5551 | TIFF: Wrong colormap |
| H_ERR_TIF_TOO_MANY_COLORS | 5552 | TIFF: Too many colors |
| H_ERR_TIF_BAD_PHOTOMETRIC | 5553 | TIFF: Wrong photometric interpretation |
| H_ERR_TIF_PHOTOMETRIC_DEPTH | 5554 | TIFF: Wrong photometric depth |
| H_ERR_TIF_NO_REGION | 5555 | TIFF: Image is no binary file |
| H_ERR_TIF_UNSUPPORTED_FORMAT | 5556 | TIFF: Image format not supported by HALCON |
| H_ERR_TIF_BAD_SPECIFICATION | 5557 | TIFF: Wrong specification of the TIFF file format |
| H_ERR_TIF_FILE_CORRUPT | 5558 | TIFF: TIFF file is corrupt |
| H_ERR_TIF_TAG_UNDEFINED | 5559 | TIFF: A required TIFF tag is missing in the TIFF file |
| H_ERR_BMP_NO_BMP_PICTURE | 5560 | File is no BMP-File |
| H_ERR_BMP_READ_ERROR_EOF | 5561 | BMP: Premature end of file |
| H_ERR_BMP_INCOMPLETE_HEADER | 5562 | BMP: Incomplete header |
| H_ERR_BMP_UNKNOWN_FORMAT | 5563 | BMP: Unknown bitmap format |
| H_ERR_BMP_UNKNOWN_COMPRESSION | 5564 | BMP: Unknown compression format |
| H_ERR_BMP_COLORMAP | 5565 | BMP: Wrong color table |
| H_ERR_BMP_WRITE_ERROR | 5566 | BMP: Write error on output |
| H_ERR_BMP_NO_REGION | 5567 | BMP: File does not contain a binary image |
| H_ERR_JPG_COMP_NUM | 5570 | JPEG: wrong number of components in image |
| H_ERR_JPGLIB_UNKNOWN | 5571 | JPEG: unknown error from libjpeg |
| H_ERR_JPGLIB_NOTIMPL | 5572 | JPEG: no implemented feature in libjpeg |
| H_ERR_JPGLIB_FILE | 5573 | JPEG: file access error in libjpeg |
| H_ERR_JPGLIB_TMPFILE | 5574 | JPEG: tmp file access error in libjpeg |
| H_ERR_JPGLIB_MEMORY | 5575 | JPEG: memory error in libjpeg |
| H_ERR_JPGLIB_INFORMAT | 5576 | JPEG: Error in input image |
| H_ERR_PNG_NO_PNG_FILE | 5580 | PNG: File is not a PNG file |
| H_ERR_PNG_UNKNOWN_INTERLACE_TYPE | 5581 | PNG: Unknown interlace type |
| H_ERR_PNG_UNSUPPORTED_COLOR_TYPE | 5582 | PNG: Unsupported color type |
| H_ERR_PNG_NO_REGION | 5583 | PNG: Image is no binary file |
| H_ERR_PNG_SIZE_TOO_BIG | 5584 | PNG: Maximal image size exceeded |
| H_ERR_TIF_TAG_ACCESS | 5587 | TIFF: Error accessing a TIFF tag |
| H_ERR_TIF_TAG_DATATYPE | 5588 | TIFF: Wrong datatype for specified TIFF tag |
| H_ERR_TIF_TAG_UNSUPPORTED | 5589 | TIFF: Requested TIFF tag not supported by HALCON |
| H_ERR_JP2_CORRUPT | 5590 | JPEG-2000: File corrupt |
| H_ERR_JP2_PREC_TOO_HIGH | 5591 | JPEG-2000: Image has more than 28 significant bits |
| H_ERR_JP2_ENCODING_ERROR | 5592 | JPEG-2000: Error while encoding |
| H_ERR_JP2_SIZE_TOO_BIG | 5593 | JPEG-2000: Maximal image size exceeded |
| H_ERR_HOBJ_NOT_ONLY_IMAGES | 5599 | HOBJ: File does not contain only images |
| H_ERR_SOCKET_BLOCK | 5600 | Socket can not be set to block |
| H_ERR_SOCKET_UNBLOCK | 5601 | Socket can not be set to unblock |
| H_ERR_SOCKET_NO_CPAR | 5602 | Received data is no tuple |

| Error Name | Code | Description |
|----------------------------------|------|--|
| H_ERR_SOCKET_NO_IMAGE | 5603 | Received data is no image |
| H_ERR_SOCKET_NO_RL | 5604 | Received data is no region |
| H_ERR_SOCKET_NO_XLD | 5605 | Received data is no xld object |
| H_ERR_SOCKET_READ_DATA_FAILED | 5606 | Error while reading from socket |
| H_ERR_SOCKET_WRITE_DATA_FAILED | 5607 | Error while writing to socket |
| H_ERR_SOCKET_WRONG_BYTE_NUMBER | 5608 | Illegal number of bytes with get_rl |
| H_ERR_SOCKET_BUFFER_OVERFLOW | 5609 | Buffer overflow in read_data |
| H_ERR_SOCKET_CANT_ASSIGN_FD | 5610 | Socket can not be created |
| H_ERR_SOCKET_CANT_BIND | 5611 | Bind on socket failed |
| H_ERR_SOCKET_CANT_GET_PORTNUMBER | 5612 | Socket information is not available |
| H_ERR_SOCKET_CANT_LISTEN | 5613 | Socket cannot listen for incoming connections |
| H_ERR_SOCKET_CANT_ACCEPT | 5614 | Connection could not be accepted |
| H_ERR_SOCKET_CANT_CONNECT | 5615 | Connection request failed |
| H_ERR_SOCKET_GETHOSTBYNAME | 5616 | Hostname could not be resolved |
| H_ERR_SOCKET_ILLEGAL_TUPLE_TYPE | 5618 | Unknown tuple type on socket |
| H_ERR_SOCKET_TIMEOUT | 5619 | Timeout occurred on socket |
| H_ERR_SOCKET_NA | 5620 | No more sockets available |
| H_ERR_SOCKET_NI | 5621 | Socket is not initialized |
| H_ERR_SOCKET_OOR | 5622 | Invalid socket |
| H_ERR_SOCKET_IS | 5623 | Socket is NULL |
| H_ERR_SOCKET_DATA_TOO_LARGE | 5624 | Received data type is too large |
| H_ERR_SOCKET_WRONG_TYPE | 5625 | Wrong socket protocol |
| H_ERR_SOCKET_NO_PACKED_DATA | 5626 | Received data does not contain packed data |
| H_ERR_SOCKET_PARAM_FAILED | 5627 | Error when handling the parameter |
| H_ERR_SOCKET_FORMAT_MISMATCH | 5628 | Format specification does not match the data |
| H_ERR_SOCKET_INVALID_FORMAT | 5629 | Invalid format specification |
| H_ERR_SOCKET_NO_SERIALIZED_ITEM | 5630 | Received data is no serialized item |
| H_ERR_SOCKET_TLS_CONTEXT | 5631 | Could not initialize TLS library |
| H_ERR_SOCKET_TLS_CERT_KEY | 5632 | Invalid TLS Certificate or private Key |
| H_ERR_SOCKET_TLS_HANDSHAKE | 5633 | TLS handshake failed |
| H_ERR_XLD_DATA_TOO_LARGE | 5678 | XLD object data can only be read by HALCON XL |
| H_ERR_ARCINFO_TOO_MANY_XLDS | 5700 | Too many contours/polygons for this file format |
| H_ERR_QUAT_WRONG_VERSION | 5750 | The version of the quaternion is not supported |
| H_ERR_QUAT_NOSITEM | 5751 | Serialized item does not contain a valid quaternion |
| H_ERR_HOM_MAT2D_WRONG_VERSION | 5752 | The version of the homogeneous matrix is not supported |
| H_ERR_HOM_MAT2D_NOSITEM | 5753 | Serialized item does not contain a valid homogeneous matrix |
| H_ERR_HOM_MAT3D_WRONG_VERSION | 5754 | The version of the homogeneous 3D matrix is not supported |
| H_ERR_HOM_MAT3D_NOSITEM | 5755 | Serialized item does not contain a valid homogeneous 3D matrix |
| H_ERR_TUPLE_WRONG_VERSION | 5756 | The version of the tuple is not supported |
| H_ERR_TUPLE_NOSITEM | 5757 | Serialized item does not contain a valid tuple |
| H_ERR_TUPLE_DTLFTHV | 5758 | Number too big for a string to number conversion (overflow) |
| H_ERR_POSE_WRONG_VERSION | 5759 | The version of the camera parameters (pose) is not supported |
| H_ERR_POSE_NOSITEM | 5760 | Serialized item does not contain valid camera parameters (pose) |
| H_ERR_CAM_PAR_WRONG_VERSION | 5761 | The version of the internal camera parameters is not supported |
| H_ERR_CAM_PAR_NOSITEM | 5762 | Serialized item does not contain valid internal camera parameters |
| H_ERR_DUAL_QUAT_WRONG_VERSION | 5763 | The version of the dual quaternion is not supported |
| H_ERR_DUAL_QUAT_NOSITEM | 5764 | Serialized item does not contain a valid dual quaternion |
| H_ERR_NP | 6000 | Access to undefined memory area |
| H_ERR_MEM | 6001 | Not enough memory available |
| H_ERR_ICM | 6002 | Memory partition on heap has been overwritten |
| H_ERR_WMS | 6003 | HALloc: 0 bytes requested |
| H_ERR_NOTMP | 6004 | Tmp-memory management: Call freeing memory although nothing had been allocated |
| H_ERR_TMPNULL | 6005 | Tmp-memory management: Null pointer while freeing |

| Error Name | Code | Description |
|----------------------------------|------|--|
| H_ERR_CNFMEM | 6006 | Tmp-memory management: could not find memory element |
| H_ERR_WMT | 6007 | Memory management: wrong memory type allocated |
| H_ERR_MEM_VID | 6021 | Not enough video memory available |
| H_ERR_IAD | 6040 | System parameter for memory-allocation inconsistent |
| H_ERR_NRA | 6041 | No memory block allocated at last |
| H_ERR_INVALID_ALIGN | 6042 | Invalid alignment |
| H_ERR_NULL_PTR | 6043 | Function was given a NULL pointer as input |
| H_ERR_CP_FAILED | 6500 | Process creation failed |
| H_ERR_WOCPI | 7000 | Wrong index for output control parameter |
| H_ERR_WOCPVN | 7001 | Wrong number of values: output control parameter (see: HPut*Par) |
| H_ERR_WOCPT | 7002 | Wrong type: output control parameter (see: HPut*Par) |
| H_ERR_WKT | 7003 | Wrong data type for object key (input objects) |
| H_ERR_IOOR | 7004 | Range for integer had been passed |
| H_ERR_IHV | 7005 | Inconsistent HALCON version |
| H_ERR_NISS | 7006 | Not enough memory for strings allocated |
| H_ERR_PROC_NULL | 7007 | Internal error: Proc is NULL |
| H_ERR_UNKN | 7105 | Unknown symbolic object key (input objects) |
| H_ERR_WOON | 7200 | Wrong number of output object parameter |
| H_ERR_OTSE | 7400 | System error: output type <string> expected |
| H_ERR_OTLE | 7401 | System error: output type <long> expected |
| H_ERR_OTFE | 7402 | System error: output type <float> expected |
| H_ERR_OPINP | 7403 | Object parameter is a zero pointer ('_' not allowed) |
| H_ERR_TWC | 7404 | Tuple had been deleted; values are not valid any more |
| H_ERR_CNN_DATA | 7701 | CNN: Internal data error |
| H_ERR_CNN_MEM | 7702 | CNN: Invalid memory type |
| H_ERR_CNN_IO_INVALID | 7703 | CNN: Invalid data serialization |
| H_ERR_CNN_IMPL_NOT_AVAILABLE | 7704 | CNN: Implementation not available |
| H_ERR_CNN_NUM_INPUTS_INVALID | 7705 | Wrong number of input data |
| H_ERR_CNN_IMPL_INVALID | 7706 | CNN: Invalid implementation type selected |
| H_ERR_CNN_TRAINING_NOT_SUP | 7707 | CNN: Training is not supported by the current environment |
| H_ERR_CNN_GPU_REQUIRED | 7708 | For this operation a GPU with certain minimal hardware specifications is required (See installation guide) |
| H_ERR_CNN_CUDA_LIBS_MISSING | 7709 | For this operation a suitable GPU and the corresponding CUDA libraries need to be available (See installation guide) |
| H_ERR_OCR_CNN_RE | 7710 | OCR File: Error while reading classifier |
| H_ERR_OCR_CNN_WGPN | 7711 | Wrong generic parameter name |
| H_ERR_OCR_CNN_EXCLUSIV_PARAM | 7712 | One of the generic parameters returns several values and has to be used exclusively |
| H_ERR_CNN_WGPN | 7713 | Wrong generic parameter name |
| H_ERR_CNN_INVALID_LABELS | 7714 | Invalid label |
| H_ERR_OCR_CNN_FILE_WRONG_VERSION | 7715 | OCR File: Wrong file version |
| H_ERR_CNN_MULTIPLE_CLASSES | 7716 | Invalid classes: At least one class occurs twice |
| H_ERR_CNN_CUBLAS_LIBS_MISSING | 7717 | For this operation the cuBLAS library needs to be available (See installation guide) |
| H_ERR_CNN_CUDNN_LIBS_MISSING | 7718 | For this operation the cuDNN library needs to be available (See installation guide) |
| H_ERR_OCR_FNF_FIND_TEXT_SUPPORT | 7719 | File 'find_text_support.hotc' not found. Please place this file in the ocr subdirectory of the root directory of the HALCON installation or in the current working directory |
| H_ERR_CNN_TRAINING_FAILED | 7720 | Training step failed. This might be caused by unsuitable hyperparameters |
| H_ERR_CNN_NO_PRETRAINED_WEIGHTS | 7721 | Weights of the pretrained network have been overwritten and cannot be restored |
| H_ERR_CNN_INVALID_INPUT_SIZE | 7722 | One or more input dimensions are too small for the network |
| H_ERR_CNN_RESULT_NOT_AVAILABLE | 7723 | The requested results are not available for this network |
| H_ERR_CNN_INVALID_INPUT_DEPTH | 7724 | The number of channels of the input image must be either 1 or 3 |

| Error Name | Code | Description |
|-------------------------------------|------|--|
| H_ERR_CNN_DEPTH_NOT_AVAILABLE | 7725 | The number of channels of the input image cannot be set |
| H_ERR_CNN_INVALID_BATCH_SIZE | 7726 | Batch size smaller than subbatch size |
| H_ERR_CNN_INVALID_PARAM_SPEC | 7727 | Invalid parameter specification |
| H_ERR_CNN_EXCEEDS_MAX_MEM | 7728 | Internal memory management limit exceeded |
| H_ERR_CNN_BATCH_SIZE_OVERFLOW | 7729 | The required memory exceeds internal limits. This can be caused by very high values of batch size |
| H_ERR_CNN_INVALID_IMAGE_SIZE | 7730 | The size of input image for the model is invalid. Width and height must be divisible through the level of the last backbone layer |
| H_ERR_CNN_INVALID_LAYER_PARAM_VALUE | 7731 | The parameter value is invalid for this graph node. |
| H_ERR_CNN_INVALID_LAYER_PARAM_NUM | 7732 | The number of parameters is invalid for this graph node. |
| H_ERR_CNN_INVALID_LAYER_PARAM_TYPE | 7733 | The parameter type is invalid for this graph node. |
| H_ERR_CNN_NUM_OUTPUTS_INVALID | 7734 | Wrong number of output data |
| H_ERR_CNN_INVALID_SHAPE | 7735 | CNN: Invalid shape of input |
| H_ERR_CNN_INVALID_INPUT_DATA | 7736 | CNN: Invalid input data |
| H_ERR_CNN_CUDNN CTC_LOSS_BUGGY | 7737 | CNN: For variable input lengths the ctc loss layer only computes correct gradients if the used cuDNN version is $\geq 7.6.3$. Please upgrade cuDNN or do not use variable input lengths. |
| H_ERR_CNN_INVALID_PADDING | 7738 | CNN: Invalid padding |
| H_ERR_CNN_IO_INVALID_LAYER_TYPE | 7740 | CNN: Invalid layer type serialization |
| H_ERR_CNN_INFERENCE_FAILED | 7741 | CNN: Inference failed. This might be caused by bad weights created by unsuitable hyperparameters during the training |
| H_ERR_CNN_RUNTIME_FAILED | 7742 | CNN: Runtime unsupported on this machine |
| H_ERR_GRAPH_INTERNAL | 7751 | Graph: Internal error |
| H_ERR_GRAPH_IO_INVALID | 7752 | Graph: Invalid data serialization |
| H_ERR_GRAPH_INVALID_INDEX | 7753 | Graph: Invalid index |
| H_ERR_CNNGRAPH_INTERNAL | 7760 | CNN graph: Internal error |
| H_ERR_CNNGRAPH_IO_INVALID | 7761 | CNN graph: Invalid data serialization |
| H_ERR_CNNGRAPH_LAYER_INVALID | 7762 | CNN graph: Invalid layer specification |
| H_ERR_CNNGRAPH_NOINIT | 7763 | CNN graph: Graph not initialized properly |
| H_ERR_CNNGRAPH_INVALID_MEM | 7764 | CNN graph: Invalid memory type |
| H_ERR_CNNGRAPH_INVALID_NUML | 7765 | CNN graph: Invalid number of layers |
| H_ERR_CNNGRAPH_INVALID_IDX | 7766 | CNN graph: Invalid index |
| H_ERR_CNNGRAPH_SPEC_STATUS | 7767 | CNN graph: Invalid specification state |
| H_ERR_CNNGRAPH_NOCHANGE | 7768 | CNN graph: Graph is not allowed to be changed after initialization |
| H_ERR_CNNGRAPH_PREPROC | 7769 | CNN graph: Missing preprocessing |
| H_ERR_CNNGRAPH_DEGREE | 7770 | CNN graph: Invalid vertex degree |
| H_ERR_CNNGRAPH_OUTSHAPE | 7771 | CNN graph: Invalid output shape |
| H_ERR_CNNGRAPH_SPEC | 7772 | CNN graph: Invalid specification |
| H_ERR_CNNGRAPH_DEF | 7773 | CNN graph: Invalid graph definition |
| H_ERR_CNNGRAPH_NO_CLASS_CHANGE | 7774 | CNN-Graph: Architecture not suitable for the adaption of the number of output classes |
| H_ERR_CNNGRAPH_NO_IMAGE_RESIZE | 7775 | CNN-Graph: Architecture not suitable for the adaption of the image size |
| H_ERR_CNNGRAPH_AUX_INDEX_OOB | 7776 | CNN-Graph: Auxiliary output index out of bounds. |
| H_ERR_CNNGRAPH_AUX_SPEC | 7777 | CNN-Graph: Invalid graph definition. Probably the auxiliary outputs of a layer have not been connected with corresponding aux selection layers (SelectAux) or at least one aux output has not been specified during model creation (create_dl_model call). |
| H_ERR_CNNGRAPH_LAYER_UNSUPPORTED | 7778 | CNN-Graph: At least one layer is unsupported for the selected runtime or operation |
| H_ERR_DL_INTERNAL | 7779 | DL: Internal Error |
| H_ERR_DL_FILE_READ | 7780 | DL: Error while reading file |
| H_ERR_DL_FILE_WRITE | 7781 | DL: Error while writing file |
| H_ERR_DL_FILE_WRONG_VERSION | 7782 | DL: Wrong file version |
| H_ERR_DL_INPUTS_MISSING | 7783 | DL: Inputs missing in input dict |
| H_ERR_DL_INPUT_WRONG_BS | 7784 | DL: Inputs have incorrect batch size |

| Error Name | Code | Description |
|---|------|--|
| H_ERR_DL_INVALID_NAME | 7785 | DL: Invalid layer name |
| H_ERR_DL_DUPLICATE_NAME | 7786 | DL: Duplicate layer name |
| H_ERR_DL_INVALID_OUTPUT | 7787 | DL: Invalid output layer |
| H_ERR_DL_PARAM_NOT_AVAILABLE | 7788 | DL: Parameter is not available for this model |
| H_ERR_DL_INPUT_WRONG_LENGTH | 7789 | DL: Tuple inputs have incorrect length |
| H_ERR_DL_INPUT_WRONG_TYPE | 7790 | DL: Tuple inputs have incorrect type |
| H_ERR_DL_INPUT_WRONG_VALUES | 7791 | DL: Some inputs have incorrect values |
| H_ERR_DL_CLASS_IDS_NOT_UNIQUE | 7792 | DL: Some class ids are not unique |
| H_ERR_DL_CLASS_IDS_INVALID | 7793 | DL: Some class ids have incorrect values.The expected value range is [0, 65534] |
| H_ERR_DL_CLASS_IDS_INVALID_CONV | 7794 | DL: Input data of class id conversion is invalid |
| H_ERR_DL_TYPE_ALREADY_DEFINED | 7795 | DL: Type is already defined so it cannot be changed |
| H_ERR_DL_NO_INFERENCE_INPUTS | 7796 | DL: Cannot identify inference inputs |
| H_ERR_DL_CLASS_IDS_INVALID_OVERLAP | 7797 | DL: Class ids must not overlap with ignore class ids |
| H_ERR_DL_WRONG_OUTPUT_LAYER_NUM | 7798 | DL: Tuple of output layers has incorrect length |
| H_ERR_DL_WRONG_BS_MULTIPLIER | 7799 | DL: Batch size multiplier needs to be greater than 0 |
| H_ERR_DL_INPUT_WRONG_BS_WITH_MULTIPLIER | 7800 | DL: Inputs have incorrect batch size. The number of needed inputs is defined by batch_size * batch_size_multiplier |
| H_ERR_DL_READ_ONNX | 7801 | Error occurred while reading an ONNX model |
| H_ERR_DL_CLASS_IDS_MISSING | 7802 | DL: Model has no class ids |
| H_ERR_DL_WRITE_ONNX | 7803 | Error occurred while writing an ONNX model |
| H_ERR_DL_ONNX_LOADER | 7804 | Libprotobuf for ONNX could not be loaded |
| H_ERR_DL_FPN_SCALES | 7810 | DL: min_level or max_level not compatible with backbone |
| H_ERR_DL_FPN_INVALID_BACKBONE | 7811 | DL: Backbone unusable for FPN creation |
| H_ERR_DL_FPN_INVALID_FEATURE_MAP_SIZE | 7812 | DL: Image size not compatible with backbone |
| H_ERR_DL_FPN_INVALID_LEVELS | 7813 | DL: Invalid FPN-levels. |
| H_ERR_DL_ANCHOR | 7820 | DL: Internal error with anchors |
| H_ERR_DL_DETECTOR_INVALID_PARAM | 7821 | DL: Invalid detector parameter |
| H_ERR_DL_DETECTOR_INVALID_PARAM_VALUE | 7822 | DL: Invalid detector parameter value |
| H_ERR_DL_DETECTOR_INVALID_DOCKING_LAYER | 7823 | DL: Invalid backbone docking layer names |
| H_ERR_DL_DETECTOR_INVALID_INSTANCE_TYPE | 7824 | DL: Invalid instance type |
| H_ERR_DL_NODE_MISSING_PARAM_NAME | 7830 | DL-Node: Missing generic parameter 'name'. Please specify a layer name. |
| H_ERR_DL_NODE_GENPARAM_NAME_NOT_ALLOWED | 7831 | DL-Node: No generic parameter 'name' allowed for this node. |
| H_ERR_DL_NODE_INVALID_SPEC | 7832 | DL-Node: Invalid layer specification. |
| H_ERR_DL_NODE_DUPLICATE_EDGE | 7833 | DL-Node: There can only be one direct connection between two layers. |
| H_ERR_DL_SOLVER_INVALID_TYPE | 7840 | DL: Invalid solver type. |
| H_ERR_DL_SOLVER_INVALID_UPDATE_FORMULA | 7841 | DL: Invalid solver update formula. |
| H_ERR_DL_HEATMAP_UNSUPPORTED_RUNTIME | 7850 | DL: The heatmap is unsupported with the selected runtime |
| H_ERR_DL_HEATMAP_UNSUPPORTED_MODEL_TYPE | 7851 | DL: The heatmap is not available for the selected model type |
| H_ERR_DL_HEATMAP_UNSUPPORTED_METHOD | 7852 | DL: The selected heatmap method is not supported |
| H_ERR_DL_HEATMAP_WRONG_TARGET_CLASS_ID | 7853 | DL: The selected target class is not available. Please choose a valid class id. |
| H_ERR_DL_GCAD_NETWORK_NOT_AVAILABLE | 7870 | DL: GC anomaly detection model network is not available. |
| H_ERR_DL_ANOMALY_MODEL_INTERNAL | 7880 | DL: Anomaly detection model internal error. |
| H_ERR_DL_ANOMALY_MODEL_UNTRAINED | 7881 | DL: Anomaly detection model is not yet trained. |
| H_ERR_DL_ANOMALY_MODEL_TRAINING_FAILED | 7882 | DL: Training of anomaly detection model failed. |
| H_ERR_DL_ANOMALY_MODEL_PARAM_TRAINED | 7883 | DL: Unable to set parameter in a trained anomaly detection model. |
| H_ERR_DL_ANOMALY_MODEL_RESIZE | 7884 | DL: Changing the model input size failed for the specified parameter value. |
| H_ERR_DL_ANOMALY_MODEL_DEPTH | 7885 | DL: Model input depth is not supported. |
| H_ERR_DL_ANOMALY_MODEL_INPUT_DOMAIN | 7886 | DL: The domain of the input image is empty. |
| H_ERR_DEEP_OCR_MODEL_INTERNAL | 7890 | Deep OCR internal error. |
| H_ERR_DEEP_OCR_MODEL_INVALID_ALPHABET | 7891 | Alphabet cannot contain items with a string length greater than one. |

| Error Name | Code | Description |
|---|------|---|
| H_ERR_DEEP_OCR_MODEL_INVALID_ALPHABET_IDX | 7892 | Out of bounds indexing into alphabet. |
| H_ERR_DEEP_OCR_MODEL_INVALID_MODEL_TYPE | 7893 | The type of the given Deep OCR model component is not allowed. |
| H_ERR_DEEP_OCR_MODEL_NOT_AVAILABLE | 7894 | The Deep OCR model component is not available. |
| H_ERR_DEEP_OCR_MODEL_INVALID_ALPHABET_MAPPING_NO_ALPHABET | 7895 | It is not possible to specify a mapping because there is no internal alphabet specified. |
| H_ERR_DEEP_OCR_MODEL_INVALID_ALPHABET_MAPPING_IDX | 7896 | Out of bounds index into internal alphabet given in mapping. |
| H_ERR_DEEP_OCR_MODEL_INVALID_ALPHABET_MAPPING_LEN | 7897 | The length of the mapping and the length of the internal alphabet need to be the same. |
| H_ERR_DEEP_OCR_MODEL_FILE_NOT_FOUND | 7898 | The Deep OCR model file could not be found. Deep OCR requires the installation of Deep Learning. Please make sure it is installed correctly (see Installation Guide). |
| H_ERR_DEEP_OCR_MODEL_UNKNOWN_CHAR | 7899 | Some character is not part of the internal alphabet. |
| H_ERR_DEEP_OCR_MODEL_INVALID_WORD_LENGTH | 7900 | The given word length is invalid. |
| H_ERR_DEEP_OCR_MODEL_ALPHABET_NOT_UNIQUE | 7901 | The given alphabet is not a unique list of characters |
| H_ERR_DL_MODEL_APPLY_NO_DEF_OUTPUTS | 7910 | DL: The model architecture does not allow to specify default outputs |
| H_ERR_DL_MODEL_UNSUPPORTED_GENPARAM | 7911 | DL: Unsupported generic parameter |
| H_ERR_DL_MODEL_OPERATOR_UNSUPPORTED | 7912 | DL: Operator does not support the model type |
| H_ERR_DL_MODEL_RUNTIME | 7913 | DL: Requested runtime cannot be set |
| H_ERR_DL_MODEL_UNSUPPORTED_GENVALUE | 7914 | DL: Unsupported generic parameter value |
| H_ERR_DL_MODEL_INVALID_NUM_SAMPLES | 7915 | DL: Invalid number of samples |
| H_ERR_DL_MODEL_CONVERTED_PARAM | 7916 | DL: Parameter unsupported for converted model |
| H_ERR_DL_MODEL_CONVERTED_UNSUPPORTED | 7917 | DL: Unsupported operation on converted model |
| H_ERR_DEEP_COUNTING_NOT_PREPARED | 7940 | The Deep Counting model is not prepared for applying on images |
| H_ERR_DEEP_COUNTING_UNSUPPORTED_BACKBONE | 7941 | The type of the backbone for Deep Counting model must be of the model type counting |
| H_ERR_DEEP_COUNTING_PREPARE_UNSUPPORTED | 7942 | The usage of preparing a Deep Counting model is not supported in this context |
| H_ERR_DEEP_COUNTING_NO_BACKBONE | 7943 | Deep Counting model has no backbone |
| H_ERR_DL_DEVICE_UNSUPPORTED_PRECISION | 7960 | DL: Unsupported device precision |
| H_ERR_DL_PRUNING_WRONG_DATA | 7980 | DL: Given pruning data and model are not compatible |
| H_ERR_DL_PRUNING_UNSUPPORTED_BY_CNN | 7981 | DL: The model architecture does not support pruning |
| H_ERR_DL_MODULE_NOT_LOADED | 7990 | DL: The DL module (libhalcondl.so/halcondl.dll) could not be loaded |
| H_ERR_WPRN | 8000 | Unknown operator name |
| H_ERR_RCNA | 8001 | register_comp_used is not activated (see set_system) |
| H_ERR_WPC | 8002 | Unknown operator class |
| H_ERR_ORMF | 8101 | convol/mask: error while opening the file |
| H_ERR_EOFRMF | 8102 | convol/mask: premature end of file |
| H_ERR_CVTRMF | 8103 | convol/mask: conversion error |
| H_ERR_LCNRMF | 8104 | convol/mask: wrong row-/column number |
| H_ERR_WCOVRMF | 8105 | convol/mask: mask size overflow |
| H_ERR_NEOFRMF | 8106 | convol/mask: too many elements entered |
| H_ERR_WRA | 8107 | convol: wrong margin type |
| H_ERR_MCNO | 8108 | convol: no mask object has got empty region |
| H_ERR_WFO | 8110 | convol: Weight factor is 0 |
| H_ERR_NWC | 8111 | convol: inconsistent number of weights |
| H_ERR_WRRV | 8112 | rank: wrong rank value |
| H_ERR_ROVFL | 8113 | convol/rank: error while handling margin |
| H_ERR_EWPMF | 8114 | Error while parsing filter mask file |
| H_ERR_WNUMM | 8120 | Wrong number of coefficients for convolution (sigma too big?) |
| H_ERR_WBEDN | 8200 | No valid ID for data set |
| H_ERR_NBEDA | 8201 | No data set active (set_bg_esti) |
| H_ERR_BEDNAU | 8202 | ID already used for data set (is not possible) |
| H_ERR_NBEDC | 8204 | No data set created (create_bg_esti) |
| H_ERR_NTM | 8205 | Not possible to pass an object list |

| Error Name | Code | Description |
|--------------------------------|------|---|
| H_ERR_WISBE | 8206 | Image has other size than the background image in data set |
| H_ERR_UDNSSBE | 8207 | Up-date-region is bigger than background image |
| H_ERR_SNBETS | 8208 | Number of statistic data sets is too small |
| H_ERR_WAMBE | 8209 | Wrong value for adapt mode |
| H_ERR_WFMBE | 8210 | Wrong value for frame mode |
| H_ERR_PE_NPCTS | 8250 | Number of point correspondences too small |
| H_ERR_PE_INVMET | 8251 | Invalid pose estimation method |
| H_ERR_OCR_MEM1 | 8300 | Maximum number of fonts exceeded |
| H_ERR_OCR_WID | 8301 | Wrong ID (Number) for font |
| H_ERR_OCR1 | 8302 | OCR internal error: wrong ID |
| H_ERR_OCR_NNI | 8303 | OCR not initialized: no font was read in |
| H_ERR_OCR_NAI | 8304 | No font activated |
| H_ERR_OCR_WTP | 8305 | OCR internal error: wrong threshold in angle determination |
| H_ERR_OCR_WF | 8306 | OCR internal error: wrong attribute |
| H_ERR_OCR_READ | 8307 | The version of the OCR classifier is not supported |
| H_ERR_OCR_NODES | 8308 | OCR File: inconsistent number of nodes |
| H_ERR_OCR_EOF | 8309 | OCR File: File too short |
| H_ERR_OCR_INC1 | 8310 | OCR: internal error 1 |
| H_ERR_OCR_INC2 | 8311 | OCR: internal error 2 |
| H_ERR_WOCRTYPE | 8312 | Wrong type of OCR tool (no 'box' or 'net') |
| H_ERR_OCR_TRF | 8313 | The version of the OCR training characters is not supported |
| H_ERR_TRF_ITL | 8314 | Image too large for training file |
| H_ERR_TRF_RTL | 8315 | Region too large for training file |
| H_ERR_TRF_PT | 8316 | Protected training file |
| H_ERR_TRF_WPW | 8317 | Wrong password for protected training file |
| H_ERR_OCR_NOSITEM | 8318 | Serialized item does not contain a valid OCR classifier |
| H_ERR_TRF_CON_EIO | 8319 | OCR training file concatenation failed: identical input and output files |
| H_ERR_OCR_MLP_NOCLASSFILE | 8320 | Invalid file format for MLP classifier |
| H_ERR_OCR_MLP_WRCLASSVERS | 8321 | The version of the MLP classifier is not supported |
| H_ERR_OCR_MLP_NOSITEM | 8322 | Serialized item does not contain a valid MLP classifier |
| H_ERR_OCR_SVM_NOCLASSFILE | 8330 | Invalid file format for SVM classifier |
| H_ERR_OCR_SVM_WRCLASSVERS | 8331 | The version of the SVM classifier is not supported |
| H_ERR_OCR_SVM_NOSITEM | 8332 | Serialized item does not contain a valid SVM classifier |
| H_ERR_OCR_KNN_NOCLASSFILE | 8333 | Invalid file format for k-NN classifier |
| H_ERR_OCR_KNN_NOSITEM | 8334 | Serialized item does not contain a valid k-NN classifier |
| H_ERR_OCR_CNN_NOCLASSFILE | 8335 | Invalid file format for CNN classifier |
| H_ERR_OCR_CNN_WRCLASSVERS | 8336 | The version of the CNN classifier is not supported |
| H_ERR_OCR_CNN_NOSITEM | 8337 | Serialized item does not contain a valid CNN classifier |
| H_ERR_OCR_RESULT_NOT_AVAILABLE | 8338 | The result is not available for the selected text segmentation method |
| H_ERR_OCV_NI | 8350 | OCV system not initialized |
| H_ERR_WOCVTYPE | 8351 | The version of the OCV tool is not supported |
| H_ERR_OCV_WNAME | 8353 | Wrong name for an OCV object |
| H_ERR_OCV_II | 8354 | Training has already been applied |
| H_ERR_OCV_NOTTR | 8355 | No training has been applied to the character |
| H_ERR_OCV_NOSITEM | 8356 | Serialized item does not contain a valid OCV tool |
| H_ERR_WLENGTH | 8370 | Wrong number of function points |
| H_ERR_NO_FUNCTION | 8371 | List of values is not a function |
| H_ERR_NOT_ASCENDING | 8372 | Wrong ordering of values (not ascending) |
| H_ERR_ILLEGAL_DIST | 8373 | Illegal distance of function points |
| H_ERR_NOT_MONOTONIC | 8374 | Function is not monotonic |
| H_ERR_WFUNCTION | 8375 | Wrong function type |
| H_ERR_SAME_XVAL_CONV | 8376 | The function contains multiple points with different x-values, that match the same value after the conversion from double to float. |
| H_ERR_GRID_CONNECT_POINTS | 8390 | The input points could not be arranged in a regular grid |

| Error Name | Code | Description |
|---------------------------|------|--|
| H_ERR_GRID_GEN_MAP | 8391 | Error while creating the output map |
| H_ERR_GRID_AUTO_ROT | 8392 | Auto rotation failed |
| H_ERR_CAL_NO_COMM_PAR | 8393 | No common camera parameters |
| H_ERR_CAL_NEGVY | 8394 | Vy must be > 0 |
| H_ERR_CAL_IDENTICAL_FP | 8395 | Same finder pattern found multiple times |
| H_ERR_CAL_LSCPNA | 8396 | Function not available for line scan cameras with perspective lenses |
| H_ERR_CAL_MARK_SEGM | 8397 | Segmentation of the calibration marks failed |
| H_ERR_CAL_CONT_EXT | 8398 | Extraction of the mark contours failed |
| H_ERR_CAL_NO_FP | 8399 | No finder pattern could be found |
| H_ERR_CAL_LCALP | 8400 | You have to indicate at least 3 calibration points |
| H_ERR_CAL_INCONSISTENT_FP | 8401 | Inconsistent finder pattern positions (image mirrored?) |
| H_ERR_CAL_NCPF | 8402 | No calibration table found |
| H_ERR_CAL_RECPF | 8403 | Error while reading calibration table description file |
| H_ERR_CAL_LTMTH | 8404 | Minimum threshold while searching for ellipses |
| H_ERR_CAL_FRCP | 8405 | Read error / format error in calibration table description file |
| H_ERR_CAL_PROJ | 8406 | Point cannot be projected |
| H_ERR_CAL_UNPRO | 8407 | Error in inverse projection |
| H_ERR_CAL_RICPF | 8408 | Not possible to open camera parameter file |
| H_ERR_CAL_FICP1 | 8409 | Format error in file: no colon |
| H_ERR_CAL_FICP2 | 8410 | Format error in file: 2. colon is missing |
| H_ERR_CAL_FICP3 | 8411 | Format error in file: semicolon is missing |
| H_ERR_CAL_REPOS | 8412 | Not possible to open camera parameter (pose) file |
| H_ERR_CAL_FOPOS | 8413 | Format error in camera parameter (pose) file |
| H_ERR_CAL_OCPDF | 8414 | Not possible to open calibration target description file |
| H_ERR_CAL_OCPPS | 8415 | Not possible to open postscript file of calibration target |
| H_ERR_CAL_EVECN | 8416 | Error while normalizing the vector |
| H_ERR_CAL_NPLAN | 8417 | Fitting of calibration target failed |
| H_ERR_CAL_NNMAR | 8418 | No next mark found |
| H_ERR_CAL_NNEQU | 8419 | Normal equation system is not solvable |
| H_ERR_CAL_QETHM | 8420 | Average quadratic error is too big for 3D position of mark |
| H_ERR_CAL_NOELL | 8421 | Non elliptic contour |
| H_ERR_CAL_WPARV | 8422 | Wrong parameter value slvand() |
| H_ERR_CAL_WFRES | 8423 | Wrong function results slvand() |
| H_ERR_CAL_ECPDI | 8424 | Distance of marks in calibration target description file is not possible |
| H_ERR_CAL_WFLA | 8425 | Specified flag for degree of freedom not valid |
| H_ERR_CAL_NOMER | 8426 | Minimum error did not fall below |
| H_ERR_CAL_WPTYT | 8427 | Wrong type in Pose (rotation / translation) |
| H_ERR_CAL_WIMSZ | 8428 | Image size does not match the measurement in camera parameters |
| H_ERR_CAL_NPILS | 8429 | Point could not be projected into linescan image |
| H_ERR_CAL_DIACM | 8430 | Diameter of calibration marks could not be determined |
| H_ERR_CAL_ORICP | 8431 | Orientation of calibration plate could not be determined |
| H_ERR_CAL_CPNII | 8432 | Calibration plate does not lie completely inside the image |
| H_ERR_CAL_WNCME | 8433 | Wrong number of calibration marks extracted |
| H_ERR_CAL_UNKPG | 8434 | Unknown name of parameter group |
| H_ERR_CAL_NEGFL | 8435 | Focal length must be non-negative |
| H_ERR_CAL_TELNA | 8436 | Function not available for cameras with telecentric lenses |
| H_ERR_CAL_LSCNA | 8437 | Function not available for line scan cameras |
| H_ERR_CAL_ELLDP | 8438 | Ellipse is degenerated to a point |
| H_ERR_CAL_NOMF | 8439 | No orientation mark found |
| H_ERR_CAL_NCONV | 8440 | Camera calibration did not converge |
| H_ERR_CAL_HYPNA | 8441 | Function not available for cameras with hypercentric lenses |
| H_ERR_CAL_DISTORT | 8442 | Point cannot be distorted |
| H_ERR_CAL_WREDGFILT | 8443 | Wrong edge filter for the mark extraction |

| Error Name | Code | Description |
|-----------------------------------|------|---|
| H_ERR_CAL_NEGPS | 8444 | Pixel size must be positive |
| H_ERR_CAL_NEGTS | 8445 | Tilt must be within the range of 0° and 90° |
| H_ERR_CAL_NEGRS | 8446 | Rot must be within the range of 0° and 360° |
| H_ERR_CAL_INVCOMP | 8447 | Invalid camera parameters |
| H_ERR_CAL_ILLFL | 8448 | Focal length must be positive |
| H_ERR_CAL_ILLMAG | 8449 | Magnification must be positive |
| H_ERR_CAL_ILLIPD | 8450 | Illegal image plane distance |
| H_ERR_CM_NOT_OPTIMIZED | 8451 | Model not optimized yet - no results can be queried |
| H_ERR_CM_NOT_POSTPROCC | 8452 | Model not postprocessed yet - no auxiliary results can be queried |
| H_ERR_CM_NOT_INTERCONN | 8453 | Calibration setup: fields of view do not intersect |
| H_ERR_CM_CAMPAR_MISMCH | 8454 | Camera type and camera parameters incompatible |
| H_ERR_CM_CAMTYP_MISMCH | 8455 | Calibration setup: incompatible camera types |
| H_ERR_CM_CAMTYP_UNSUPD | 8456 | Camera type not supported |
| H_ERR_CM_INVALID_CAMIDX | 8457 | Invalid camera index |
| H_ERR_CM_INVALID_DESCID | 8458 | Invalid calibration object index |
| H_ERR_CM_INVALID_COBJID | 8459 | Invalid calibration object pose index |
| H_ERR_CM_UNDEFINED_CAM | 8460 | Undefined camera |
| H_ERR_CM_REPEATD_INDEX | 8461 | Indices: ambiguous observation index |
| H_ERR_CM_UNDEFI_CADESC | 8462 | Undefined calibration object |
| H_ERR_CM_NO_DESCR_FILE | 8463 | Invalid file format for calibration data model |
| H_ERR_CM_WR_DESCR_VERS | 8464 | The version of the calibration data model is not supported |
| H_ERR_CM_ZERO_MOTION | 8465 | Zero-motion in line scan camera parameters |
| H_ERR_CM_MULTICAM_UNSP | 8466 | Calibration setup: multiple cameras and/or calibration objects not supported for camera type |
| H_ERR_CM_INCMPLTE_DATA | 8467 | Incomplete observation data |
| H_ERR_CSM_NO_DESCR_FIL | 8468 | Invalid file format for camera setup model |
| H_ERR_CSM_WR_DESCR_VER | 8469 | The version of the camera setup model is not supported |
| H_ERR_CM_CALTAB_NOT_AV | 8470 | Full HALCON calibration plate description required |
| H_ERR_CM_INVAL_OBSERID | 8471 | Invalid observation index |
| H_ERR_CSM_NOSITEM | 8472 | Serialized item does not contain a valid camera setup model |
| H_ERR_CM_NOSITEM | 8473 | Serialized item does not contain a valid calibration data model |
| H_ERR_CM_INV_TOOLPOSID | 8474 | Invalid tool pose index |
| H_ERR_CM_UNDEFINED_TOO | 8475 | Undefined tool pose |
| H_ERR_CM_INVLD_MODL_TY | 8476 | Feature or operation not supported for current calibration data model type |
| H_ERR_CSM_UNINIT_CAM | 8477 | The camera setup model contains an uninitialized camera |
| H_ERR_CM_NO_VALID_SOL | 8478 | The hand-eye algorithm failed to find a valid solution |
| H_ERR_CM_INVAL_OBS_POSE | 8479 | Invalid observation pose: set_calib_data_observ_pose can only be called with calibration data models that have been configured for hand-eye-calibration; please use find_calib_object or set_calib_data_observ_points |
| H_ERR_CM_TOO_FEW_POSES | 8480 | Not enough calibration object poses: For the hand-eye-calibration at least three calibration object poses are necessary |
| H_ERR_CM_UNDEF_CAM_TYP | 8481 | Undefined camera type |
| H_ERR_SM_INVLD_IMG_PAIRS_DISP_VAL | 8482 | Number of image pairs does not correspond to the number of disparity values |
| H_ERR_SM_INVLD_DISP_VAL | 8483 | Wrong value of stereo model parameter 'min_disparity' or 'max_disparity' |
| H_ERR_SM_NO_IM_PAIR | 8484 | No camera pair set by set_stereo_model_image_pairs |
| H_ERR_SM_NO_VIS_COLOR | 8485 | No reconstructed point is visible for coloring |
| H_ERR_SM_NO_RECONSTRUCT | 8486 | No camera pair yields reconstructed points (please check parameters of disparity method or bounding box) |
| H_ERR_SM_INVLD_BB_PARTITION | 8487 | Partitioning of bounding box is too fine (please adapt the parameter 'resolution' or the bounding box) |
| H_ERR_SM_INVLD_DISP_RANGE | 8488 | Disparity range as calculated by the bounding box and the parameter 'rectif_sub_sampling' exceeds the maximum permitted |

| Error Name | Code | Description |
|-------------------------------|------|--|
| H_ERR_SM_INVLD_BIN_PAR | 8489 | The parameter to be set is not supported by the chosen disparity method |
| H_ERR_SM_INVLD_MODL_TY | 8490 | Feature or operation not supported for current stereo model type |
| H_ERR_SM_NOT_PERSISTEN | 8491 | Feature or operation available only in 'persistent' mode |
| H_ERR_SM_INVLD_BOU_BOX | 8492 | Invalid bounding box |
| H_ERR_SR_INVLD_IMG_SIZ | 8493 | Image sizes must be identical with the corresponding camera parameters from the camera setup |
| H_ERR_SR_BBOX_BHND_CAM | 8494 | Bounding box lies partially or completely behind (for hyper-centric lenses: in front of) the base line of at least one camera pair |
| H_ERR_CAL_AMBIGUOUS | 8495 | Ambiguous calibration: Please, recalibrate with improved input data! |
| H_ERR_CAL_PCPND | 8496 | Pose of calibration plate could not be determined! |
| H_ERR_CAL_FAILED | 8497 | Calibration failed: Please check your input data and calibrate again! |
| H_ERR_CAL_MISSING_DATA | 8498 | No observation data supplied! |
| H_ERR_CAL_FEWER_FOUR | 8499 | The calibration object has to be seen at least once by every camera, if less than four cameras are used |
| H_ERR_NOAP | 8500 | Invalid file format for template |
| H_ERR_WPFV | 8501 | The version of the template is not supported |
| H_ERR_MATCH_MODE | 8502 | Error during changing the file mode (t/b) |
| H_ERR_MATCH_OOR | 8503 | Inconsistent match file: coordinates out of range |
| H_ERR_NOTAP | 8505 | The image(s) is not a pyramid (wrong zooming factor?) |
| H_ERR_NGTPTS | 8506 | Number of template points too small |
| H_ERR_PDTL | 8507 | Template data can only be read by HALCON XL |
| H_ERR_NCC_NOSITEM | 8508 | Serialized item does not contain a valid NCC model |
| H_ERR_MATCH_NOSITEM | 8509 | Serialized item does not contain a valid template |
| H_ERR_NTPTS | 8510 | Number of shape model points too small |
| H_ERR_CGSMM | 8511 | Gray-value-based and color-based shape models cannot be searched simultaneously |
| H_ERR_SMTL | 8512 | Shape model data can only be read by HALCON XL |
| H_ERR_SMNXL | 8513 | Shape model was not created from XLDs |
| H_ERR_SM_NOSITEM | 8514 | Serialized item does not contain a valid shape model |
| H_ERR_SM_CL_CONT | 8515 | Shape model contour too near to clutter region |
| H_ERR_SM_NO_CLUT | 8516 | Shape model does not contain clutter parameters |
| H_ERR_SM_SAME_CL | 8517 | Activation status for the usage of clutter parameters is not identical for all shape models |
| H_ERR_SM_WRONG_CLCO | 8518 | Shape model has an invalid clutter contrast |
| H_ERR_FIND_BOX_UNSUP_GENPARAM | 8520 | Box Finder: Unsupported generic parameter |
| H_ERR_COMP_DRT | 8530 | Initial components have different region types |
| H_ERR_COMP_SAMF | 8531 | Solution of ambiguous matches failed |
| H_ERR_IGF_NC | 8532 | Computation of the incomplete gamma function not converged |
| H_ERR_MSA_TMN | 8533 | Too many nodes while computing the minimum spanning arborescence |
| H_ERR_CTTL | 8534 | Component training data can only be read by HALCON XL |
| H_ERR_CMTL | 8535 | Component model data can only be read by HALCON XL |
| H_ERR_COMP_NOSITEM | 8536 | Serialized item does not contain a valid component model |
| H_ERR_TRAIN_COMP_NOSITEM | 8537 | Serialized item does not contain a valid component training result |
| H_ERR_VARIATION_WS | 8540 | Size of the training image and the variation model differ |
| H_ERR_VARIATION_PREP | 8541 | Variation model has not been prepared for segmentation |
| H_ERR_VARIATION_WRMD | 8542 | Invalid variation model training mode |
| H_ERR_VARIATION_NOVF | 8543 | Invalid file format for variation model |
| H_ERR_VARIATION_WVVF | 8544 | The version of the variation model is not supported |
| H_ERR_VARIATION_TRDC | 8545 | Training data has already been cleared |
| H_ERR_VARIATION_NOSITEM | 8546 | Serialized item does not contain a valid variation model |
| H_ERR_MEASURE_NA | 8550 | No more measure objects available |

| Error Name | Code | Description |
|---|------|---|
| H_ERR_MEASURE_NI | 8551 | Measure object is not initialized |
| H_ERR_MEASURE_OOR | 8552 | Invalid measure object |
| H_ERR_MEASURE_IS | 8553 | Measure object is NULL |
| H_ERR_MEASURE_WS | 8554 | Measure object has wrong image size |
| H_ERR_MEASURE_NO_MODEL_FILE | 8555 | Invalid file format for measure object |
| H_ERR_MEASURE_WRONG_VERSION | 8556 | The version of the measure object is not supported |
| H_ERR_MEASURE_TL | 8557 | Measure object data can only be read by HALCON XL |
| H_ERR_MEASURE_NOSITEM | 8558 | Serialized item does not contain a valid measure object |
| H_ERR_METROLOGY_MODEL_NI | 8570 | Metrology model is not initialized |
| H_ERR_METROLOGY_OBJECT_INVALID | 8572 | Invalid metrology object |
| H_ERR_METROLOGY_FIT_NOT_ENOUGH_MEASURES | 8573 | Not enough valid measures for fitting the metrology object |
| H_ERR_METROLOGY_NO_MODEL_FILE | 8575 | Invalid file format for metrology model |
| H_ERR_METROLOGY_WRONG_VERSION | 8576 | The version of the metrology model is not supported |
| H_ERR_METROLOGY_NO_FUZZY_FUNC | 8577 | Fuzzy function is not set |
| H_ERR_METROLOGY_NOSITEM | 8578 | Serialized item does not contain a valid metrology model |
| H_ERR_METROLOGY_UNDEF_CAMPAR | 8579 | Camera parameters are not set |
| H_ERR_METROLOGY_UNDEF_POSE | 8580 | Pose of the measurement plane is not set |
| H_ERR_METROLOGY_SET_MODE | 8581 | Mode of metrology model cannot be set since an object has already been added |
| H_ERR_METROLOGY_OP_NOT_ALLOWED | 8582 | If the pose of the metrology object has been set several times, the operator is not longer allowed |
| H_ERR_METROLOGY_MULTI_POSE_CAM_PAR | 8583 | All objects of a metrology model must have the same world pose and camera parameters |
| H_ERR_METROLOGY_WRONG_INPUT_MODE | 8584 | The input type does not correspond to the input type set for the metrology model |
| H_ERR_DLOPEN | 8600 | Dynamic library could not be opened |
| H_ERR_DLCLOSE | 8601 | Dynamic library could not be closed |
| H_ERR_DLLOOKUP | 8602 | Symbol not found in dynamic library |
| H_ERR_COMPONENT_NOT_INSTALLED | 8603 | Interface library not available. Check www.mvtec.com/download for additional interfaces |
| H_ERR_EAD_CAL_NII | 8650 | Not enough information for radiometric calibration |
| H_ERR_WGSMFV | 8670 | The version of the shape model result is not supported |
| H_ERR_GSM_INVALID_RES_SCALE | 8671 | Restrict scale parameter outside the trained range |
| H_ERR_GSM_INVALID_ANGLE | 8672 | Angle parameter outside the trained range |
| H_ERR_GSM_NEEDS_TRAINING | 8673 | Shape model needs training |
| H_ERR_GSM_CONTRAST_HYS | 8674 | contrast_high cannot be smaller than contrast_low |
| H_ERR_GSM_CONTRAST_MIN_CONTRAST | 8675 | Neither contrast_low nor contrast_high can be smaller than min_contrast |
| H_ERR_GSM_ISO_SCALE_PAIR | 8676 | iso_scale_max cannot be smaller than iso_scale_min |
| H_ERR_GSM_ANISO_SCALE_ROW | 8677 | scale_row_max cannot be smaller than scale_row_min |
| H_ERR_GSM_ANISO_SCALE_COLUMN | 8678 | scale_column_max cannot be smaller than scale_column_min |
| H_ERR_GSM_ISO_NOT_SET | 8679 | Isotropic scaling not set |
| H_ERR_GSM_ANISO_NOT_SET | 8680 | Anisotropic scaling not set |
| H_ERR_GSM_INVALID_METRIC_XLD | 8681 | No edge direction available to change shape matching metric |
| H_ERR_GSM_SAME_IDENTIFIER | 8682 | Shape models with the same identifier cannot be searched simultaneously |
| H_ERR_BAR_WNOM | 8701 | Wrong number of modules |
| H_ERR_BAR_WNOE | 8702 | Wrong number of elements |
| H_ERR_BAR_UNCHAR | 8703 | Unknown character (for this code) |
| H_ERR_BAR_WRONGDESCR | 8705 | Wrong name for attribute in barcode descriptor |
| H_ERR_BAR_EL_LENGTH | 8706 | Wrong thickness of element |
| H_ERR_BAR_NO_REG | 8707 | No region found |
| H_ERR_BAR_WRONGCODE | 8708 | Wrong type of bar code |
| H_ERR_BAR_INTERNAL | 8709 | Internal error in bar code reader |
| H_ERR_BAR_NO_DECODED_SCANLINE | 8710 | Bar code candidate does not contain a decoded scanline |
| H_ERR_BC_EMPTY_MODEL_LIST | 8721 | List of bar code models is empty |
| H_ERR_BC_TRAIN_ONLY_SINGLE | 8722 | Training cannot be done for multiple bar code types |

| Error Name | Code | Description |
|----------------------------------|------|--|
| H_ERR_BC_GET_SPECIFIC | 8723 | Cannot get bar code type specific parameter with get_bar_code_param. Use get_bar_code_param_specific |
| H_ERR_BC_GET_OBJ_MULTI | 8724 | Cannot get this object for multiple bar code types. Try again with single bar code type |
| H_ERR_BC_WR_FILE_FORMAT | 8725 | Invalid file format for bar code model |
| H_ERR_BC_WR_FILE_VERS | 8726 | The version of the bar code model is not supported |
| H_ERR_BC_NOT_PERSISTANT | 8727 | Feature or operation available only in 'persistent' mode |
| H_ERR_BC_GRAY_OUT_OF_RANGE | 8728 | Incorrect index of scanline's gray values |
| H_ERR_NO_PERSISTENT_OP_CALL | 8729 | Neither find_bar_code nor decode_bar_code_rectanlge2 have been called in persistent mode on this model |
| H_ERR_BC_ZOOMED_ABORTED | 8730 | The zoomed barcode algorithm has been aborted |
| H_ERR_BC_ZOOMED_INVALID_INPUT | 8731 | zoomed barcode: Invalid input data. |
| H_ERR_BC_XCORR_INVALID_INPUT | 8740 | Barcode: Invalid inputs for NCC |
| H_ERR_BC_XCORR_TOO_MANY_BAD_ROWS | 8741 | Barcode: Too many invalid rows during NCC |
| H_ERR_BC_XCORR_NO_CORRELATION | 8742 | Barcode: No correlation found during NCC |
| H_ERR_INVALID_SYNTAX_DICTIONARY | 8743 | Invalid GS1 Application Identifier Syntax Dictionary |
| H_ERR_BAR2D_UNKNOWN_TYPE | 8800 | Specified code type is not supported |
| H_ERR_BAR2D_WRONG_FOREGROUND | 8801 | Wrong foreground specified |
| H_ERR_BAR2D_WRONG_SIZE | 8802 | Wrong matrix size specified |
| H_ERR_BAR2D_WRONG_SHAPE | 8803 | Wrong symbol shape specified |
| H_ERR_BAR2D_WRONG_PARAM_NAME | 8804 | Wrong generic parameter name |
| H_ERR_BAR2D_WRONG_PARAM_VAL | 8805 | Wrong generic parameter value |
| H_ERR_BAR2D_WRONG_MODE | 8806 | Wrong symbol printing mode |
| H_ERR_BAR2D_SYMBOL_ON_BORDER | 8807 | Symbol region too near to image border |
| H_ERR_BAR2D_MODULE_CONT_NUM | 8808 | No rectangular modul boundaries found |
| H_ERR_BAR2D_SYMBOL_FINDER | 8809 | Couldn't identify symbol finder |
| H_ERR_BAR2D_SYMBOL_DIMENSION | 8810 | Symbol region with wrong dimension |
| H_ERR_BAR2D_CLASSIF_FAILED | 8811 | Classification failed |
| H_ERR_BAR2D_DECODING_FAILED | 8812 | Decoding failed |
| H_ERR_BAR2D_DECODING_READER | 8813 | Reader programming not supported |
| H_ERR_DC2D_GENERAL | 8820 | General 2d data code error |
| H_ERR_DC2D_BROKEN_SIGN | 8821 | Corrupt signature of 2d data code handle |
| H_ERR_DC2D_INVALID_HANDLE | 8822 | Invalid 2d data code handle |
| H_ERR_DC2D_EMPTY_MODEL_LIST | 8823 | List of 2d data code models is empty |
| H_ERR_DC2D_NOT_INITIALIZED | 8824 | Access to uninitialized (or not persistent) internal data |
| H_ERR_DC2D_INVALID_CANDIDATE | 8825 | Invalid 'Candidate' parameter |
| H_ERR_DC2D_INDEX_PARNUM | 8826 | It's not possible to return more than one parameter for several candidates |
| H_ERR_DC2D_EXCLUSIV_PARAM | 8827 | One of the parameters returns several values and has to be used exclusively for a single candidate |
| H_ERR_DC2D_DEF_SET_NOT_FIRST | 8828 | Parameter for default settings must be the first in the parameter list |
| H_ERR_DC2D_INTERNAL_UNEXPECTED | 8829 | Unexpected 2d data code error |
| H_ERR_DC2D_WRONG_PARAM_VALUE | 8830 | Invalid parameter value |
| H_ERR_DC2D_WRONG_PARAM_NAME | 8831 | Unknown parameter name |
| H_ERR_DC2D_WRONG_POLARITY | 8832 | Invalid value for 'polarity' |
| H_ERR_DC2D_WRONG_SYMBOL_SHAPE | 8833 | Invalid value for 'symbol_shape' |
| H_ERR_DC2D_WRONG_SYMBOL_SIZE | 8834 | Invalid symbol size |
| H_ERR_DC2D_WRONG_MODULE_SIZE | 8835 | Invalid module size |
| H_ERR_DC2D_WRONG_MODULE_SHAPE | 8836 | Invalid value for 'module_shape' |
| H_ERR_DC2D_WRONG_ORIENTATION | 8837 | Invalid value for 'orientation' |
| H_ERR_DC2D_WRONG_CONTRAST | 8838 | Invalid value for 'contrast_min' |
| H_ERR_DC2D_WRONG_MEAS_THRESH | 8839 | Invalid value for 'measure_thresh' |
| H_ERR_DC2D_WRONG_ALT_MEAS_RED | 8840 | Invalid value for 'alt_measure_red' |
| H_ERR_DC2D_WRONG_SLANT | 8841 | Invalid value for 'slant_max' |
| H_ERR_DC2D_WRONG_L_DIST | 8842 | Invalid value for 'L_dist_max' |
| H_ERR_DC2D_WRONG_L_LENGTH | 8843 | Invalid value for 'L_length_min' |

| Error Name | Code | Description |
|--|------|---|
| H_ERR_DC2D_WRONG_GAP | 8844 | Invalid module gap |
| H_ERR_DC2D_WRONG_DEF_SET | 8845 | Invalid value for 'default_parameters' |
| H_ERR_DC2D_WRONG_TEXTURED | 8846 | Invalid value for 'back_texture' |
| H_ERR_DC2D_WRONG_MIRRORED | 8847 | Invalid value for 'mirrored' |
| H_ERR_DC2D_WRONG_CLASSIFICATOR | 8848 | Invalid value for 'classifier' |
| H_ERR_DC2D_WRONG_PERSISTENCE | 8849 | Invalid value for 'persistence' |
| H_ERR_DC2D_WRONG_MODEL_TYPE | 8850 | Invalid model type |
| H_ERR_DC2D_WRONG_MOD_ROI_PART | 8851 | Invalid value for 'module_roi_part' |
| H_ERR_DC2D_WRONG_FP_TOLERANCE | 8852 | Invalid value for 'finder_pattern_tolerance' |
| H_ERR_DC2D_WRONG_MOD_ASPECT | 8853 | Invalid value for 'mod_aspect_max' |
| H_ERR_DC2D_WRONG_SM_ROBUSTNESS | 8854 | Invalid value for 'small_modules_robustness' |
| H_ERR_DC2D_WRONG_CONTRAST_TOL | 8855 | Invalid 'contrast_tolerance' |
| H_ERR_DC2D_WRONG_AP_TOLERANCE | 8856 | Invalid value for 'alternating_pattern_tolerance' |
| H_ERR_DC2D_READ_HEAD_FORMAT | 8860 | Invalid header in 2d data code model file |
| H_ERR_DC2D_READ_HEAD_SIGN | 8861 | Invalid code signature in 2d data code model file |
| H_ERR_DC2D_READ_LINE_FORMAT | 8862 | Corrupted line in 2d data code model file |
| H_ERR_DC2D_WRONG_MODULE_ASPECT | 8863 | Invalid module aspect ratio |
| H_ERR_DC2D_WRONG_LAYER_NUM | 8864 | Invalid layer num |
| H_ERR_DCD_READ_WRONG_VERSION | 8865 | Wrong data code model file version |
| H_ERR_DC2D_NOSITEM | 8866 | Serialized item does not contain a valid 2D data code model |
| H_ERR_DC2D_WR_FILE_FORMAT | 8867 | Invalid file format for data code model |
| H_ERR_SM3D_WRONG_PARAM_NAME | 8900 | Unknown parameter name |
| H_ERR_SM3D_WRONG_NUM_LEVELS | 8901 | Invalid value for 'num_levels' |
| H_ERR_SM3D_WRONG_OPTIMIZATION | 8902 | Invalid value for 'optimization' |
| H_ERR_SM3D_WRONG_METRIC | 8903 | Invalid value for 'metric' |
| H_ERR_SM3D_WRONG_MIN_FACE_ANGLE | 8904 | Invalid value for 'min_face_angle' |
| H_ERR_SM3D_WRONG_MIN_SIZE | 8905 | Invalid value for 'min_size' |
| H_ERR_SM3D_WRONG_MODEL_TOLERANCE | 8906 | Invalid value for 'model_tolerance' |
| H_ERR_SM3D_WRONG_FAST_POSE_REF | 8907 | Invalid value for 'fast_pose_refinement' |
| H_ERR_SM3D_WRONG_LOWEST_MODEL_LEVEL | 8908 | Invalid value for 'lowest_model_level' |
| H_ERR_SM3D_WRONG_PART_SIZE | 8909 | Invalid value for 'part_size' |
| H_ERR_SM3D_PROJECTION_TOO_LARGE | 8910 | The projected model is too large (the value for DistMin or the image size in CamParam is too small) |
| H_ERR_SM3D_WRONG_OPENGL_ACCURACY | 8911 | Invalid value for 'opengl_accuracy' |
| H_ERR_SM3D_WRONG_RECOMPUTE_SCORE | 8913 | Invalid value for 'recompute_score' |
| H_ERR_SM3D_WRONG_LON_MIN | 8920 | Invalid value for 'longitude_min' |
| H_ERR_SM3D_WRONG_LON_MAX | 8921 | Invalid value for 'longitude_max' |
| H_ERR_SM3D_WRONG_LAT_MIN | 8922 | Invalid value for 'latitude_min' |
| H_ERR_SM3D_WRONG_LAT_MAX | 8923 | Invalid value for 'latitude_max' |
| H_ERR_SM3D_WRONG_ROL_MIN | 8924 | Invalid value for 'cam_roll_min' |
| H_ERR_SM3D_WRONG_ROL_MAX | 8925 | Invalid value for 'cam_roll_max' |
| H_ERR_SM3D_WRONG_DIST_MIN | 8926 | Invalid value for 'dist_min' |
| H_ERR_SM3D_WRONG_DIST_MAX | 8927 | Invalid value for 'dist_max' |
| H_ERR_SM3D_WRONG_NUM_MATCHES | 8928 | Invalid value for 'num_matches' |
| H_ERR_SM3D_WRONG_MAX_OVERLAP | 8929 | Invalid value for 'max_overlap' |
| H_ERR_SM3D_WRONG_POSE_REFINEMENT | 8930 | Invalid value for 'pose_refinement' |
| H_ERR_SM3D_WRONG_COV_POSE_MODE | 8931 | Invalid value for 'cov_pose_mode' |
| H_ERR_SM3D_WRONG_OUTLIER_SUP | 8932 | Invalid value for 'outlier_suppression' |
| H_ERR_SM3D_WRONG_BORDER_MODEL | 8933 | Invalid value for 'border_model' |
| H_ERR_SM3D_UNDEFINED_POSE | 8940 | Pose is not well-defined |
| H_ERR_SM3D_NO_SM3D_FILE | 8941 | Invalid file format for 3D shape model |
| H_ERR_SM3D_WRONG_FILE_VERSION | 8942 | The version of the 3D shape model is not supported |
| H_ERR_SM3D_MTL | 8943 | 3D shape model data can only be read by HALCON XL |
| H_ERR_SM3D_NO_OM3D_FACES | 8944 | 3D object model does not contain any faces |
| H_ERR_SM3D_NOSITEM | 8945 | Serialized item does not contain a valid 3D shape model |
| H_ERR_SM3D_WRONG_UNION_ADJACENT_CONTOURS | 8946 | Invalid value for 'union_adjacent_contours' |

| Error Name | Code | Description |
|------------------------------------|------|--|
| H_ERR_DESCR_NODESCRFIL | 8960 | Invalid file format for descriptor model |
| H_ERR_DESCR_WRDESCRVERS | 8961 | The version of the descriptor model is not supported |
| H_ERR_DM_WRONG_NUM_CIRC_RADIUS | 8962 | Invalid value for 'radius' |
| H_ERR_DM_WRONG_NUM_CHECK_NEIGH | 8963 | Invalid value for 'check_neighbor' |
| H_ERR_DM_WRONG_NUM_MIN_CHECK_NEIGH | 8964 | Invalid value for 'min_check_neighbor_diff' |
| H_ERR_DM_WRONG_NUM_MIN_SCORE | 8965 | Invalid value for 'min_score' |
| H_ERR_DM_WRONG_NUM_SIGMAGRAD | 8966 | Invalid value for 'sigma_grad' |
| H_ERR_DM_WRONG_NUM_SIGMAINT | 8967 | Invalid value for 'sigma_smooth' |
| H_ERR_DM_WRONG_NUM_ALPHA | 8968 | Invalid value for 'alpha' |
| H_ERR_DM_WRONG_NUM_THRESHOLD | 8969 | Invalid value for 'threshold' |
| H_ERR_DM_WRONG_NUM_DEPTH | 8970 | Invalid value for 'depth' |
| H_ERR_DM_WRONG_NUM_TREES | 8971 | Invalid value for 'number_trees' |
| H_ERR_DM_WRONG_NUM_MIN_SCORE_DESCR | 8972 | Invalid value for 'min_score_descr' |
| H_ERR_DM_WRONG_NUM_PATCH_SIZE | 8973 | Invalid value for 'patch_size' |
| H_ERR_DM_WRONG_TILT | 8974 | Invalid value for 'tilt' |
| H_ERR_DM_WRONG_PAR_GUIDE | 8975 | Invalid value for 'guided_matching' |
| H_ERR_DM_WRONG_PAR_SUBPIX | 8976 | Invalid value for 'subpix' |
| H_ERR_DM_TOO_FEW_POINTS | 8977 | Too few feature points can be found |
| H_ERR_DM_WRONG_NUM_MINROT | 8978 | Invalid value for 'min_rot' |
| H_ERR_DM_WRONG_NUM_MAXROT | 8979 | Invalid value for 'max_rot' |
| H_ERR_DM_WRONG_NUM_MINSCALE | 8980 | Invalid value for 'min_scale' |
| H_ERR_DM_WRONG_NUM_MAXSCALE | 8981 | Invalid value for 'max_scale' |
| H_ERR_DM_WRONG_NUM_MASKSIZEGRD | 8982 | Invalid value for 'mask_size_grd' |
| H_ERR_DM_WRONG_NUM_MASKSIZESMOOTH | 8983 | Invalid value for 'mask_size_smooth' |
| H_ERR_BROKEN_MODEL | 8984 | Model broken |
| H_ERR_DM_WRONG_DESCR_TYPE | 8985 | Invalid value for 'descriptor_type' |
| H_ERR_DM_WRONG_PAR_MATCHER | 8986 | Invalid value for 'matcher' |
| H_ERR_DM_TOO_MANY_CLASSES | 8987 | Too many point classes - model storing in a file is not possible |
| H_ERR_DESCR_NOSITEM | 8988 | Serialized item does not contain a valid descriptor model |
| H_ERR_NOT_IMPL | 9000 | Function not implemented on this machine |
| H_ERR_WIT | 9001 | Image to process has wrong gray value type |
| H_ERR_WIC | 9002 | Wrong image component (see: get_system(obj_images,H)) |
| H_ERR_UNDI | 9003 | Undefined gray values |
| H_ERR_WIS | 9004 | Wrong image format for operation (too big or too small) |
| H_ERR_WCN | 9005 | Wrong number of image components for image output |
| H_ERR_STRTL | 9006 | String is too long (max. 1024 characters) |
| H_ERR_WITFO | 9007 | Wrong pixel type for this operation |
| H_ERR_NIIT | 9008 | Operation not realized yet for this pixel type |
| H_ERR_NOCIMA | 9009 | Image is no color image with three channels |
| H_ERR_DEMO_NOFG | 9010 | Image acquisition devices are not supported in the demo version |
| H_ERR_DEMO_NOPA | 9011 | Packages are not supported in the demo version |
| H_ERR_IEUNKV | 9020 | Internal error: Unknown value |
| H_ERR_WPFO | 9021 | Wrong parameter for this operation |
| H_ERR_IDTS | 9022 | Image domain too small |
| H_ERR_CNCLDRW | 9023 | Draw operator has been canceled |
| H_ERR_REGEX_MATCH | 9024 | Error during regular expression matching |
| H_ERR_STUD_OPNA | 9050 | Operator is not available in this restricted version of HALCON |
| H_ERR_STUD_PANA | 9051 | Packages are not available in this restricted version of HALCON |
| H_ERR_STUD_FGNA | 9052 | The selected image acquisition interface is not available in this restricted version of HALCON |
| H_ERR_NDPA | 9053 | No data points available |
| H_ERR_WR_OBJ_TYPE | 9054 | Type of the object is not supported |
| H_ERR_OP_DISABLED | 9055 | Operator is disabled |
| H_ERR_TMU | 9100 | Too many unknown variables in linear equation |

| Error Name | Code | Description |
|-------------------------|------|--|
| H_ERR_NUS | 9101 | No (unique) solution for the linear equation |
| H_ERR_NEE | 9102 | Too little equations in linear equation |
| H_ERR_PDDL | 9150 | Points do not define a line |
| H_ERR_MNI | 9200 | Matrix is not invertible |
| H_ERR_SVD_CNVRG | 9201 | Singular value decomposition did not converge |
| H_ERR_SVD_FEWR0W | 9202 | Matrix has too few rows for singular value partition |
| H_ERR_TQLI_CNVRG | 9203 | Eigenvalue computation did not converge |
| H_ERR_JACOBI_CNVRG | 9204 | Eigenvalue computation did not converge |
| H_ERR_MATRIX_SING | 9205 | Matrix is singular |
| H_ERR_MATCH_CNVRG | 9206 | Function matching did not converge |
| H_ERR_MAT_UNDEF | 9207 | Input matrix undefined |
| H_ERR_MAT_WDIM | 9208 | Input matrix with wrong dimension |
| H_ERR_MAT_NSQR | 9209 | Input matrix is not quadratic |
| H_ERR_MAT_FAIL | 9210 | Matrix operation failed |
| H_ERR_MAT_NPD | 9211 | Matrix is not positive definite |
| H_ERR_MAT_DBZ | 9212 | One element of the matrix is zero: Division by zero |
| H_ERR_MAT_NUT | 9213 | Matrix is not an upper triangular matrix |
| H_ERR_MAT_NLT | 9214 | Matrix is not a lower triangular matrix |
| H_ERR_MAT_NEG | 9215 | One element of the matrix is negative |
| H_ERR_MAT_UNCHAR | 9216 | Matrix file: Invalid character |
| H_ERR_MAT_NOT_COMPLETE | 9217 | Matrix file: Matrix incomplete |
| H_ERR_MAT_READ | 9218 | Invalid file format for matrix |
| H_ERR_MAT_COMPLEX | 9219 | Resulting matrix has complex values |
| H_ERR_WMATEXP | 9220 | Wrong value in matrix of exponents |
| H_ERR_MAT_WRONG_VERSION | 9221 | The version of the matrix is not supported |
| H_ERR_MAT_NOSITEM | 9222 | Serialized item does not contain a valid matrix |
| H_ERR_WNODE | 9230 | Internal error: wrong Node |
| H_ERR_CMP_INCONSISTENT | 9231 | Inconsistent red black tree |
| H_ERR_LAPACK_PAR | 9250 | Internal error: Wrong LAPACK parameter |
| H_ERR_STRI_NPNT | 9260 | Number of points too small for spherical triangulation |
| H_ERR_STRI_COLL | 9261 | First three points are collinear in spherical triangulation |
| H_ERR_STRI_IDPNT | 9262 | Spherical triangulation contains identical input points |
| H_ERR_STRI_NALLOC | 9263 | Internal error: array not allocated large enough for spherical triangulation |
| H_ERR_STRI_DEGEN | 9264 | Spherical Voronoi diagram contains degenerate triangle |
| H_ERR_STRI_ITRI | 9265 | Internal error: inconsistent spherical triangulation |
| H_ERR_STRI_SELFINT | 9266 | Spherical Voronoi diagram contains self-intersecting polygon |
| H_ERR_STRI_INCONS | 9267 | Internal error: inconsistent spherical polygon data |
| H_ERR_STRI_AMBINT | 9268 | Internal error: Ambiguous great circle arc intersection |
| H_ERR_STRI_AMBARC | 9269 | Internal error: Ambiguous great circle arc |
| H_ERR_STRI_ILLPAR | 9270 | Internal error: Illegal parameter |
| H_ERR_TRI_NPNT | 9280 | Not enough points for planar triangular meshing |
| H_ERR_TRI_COLL | 9281 | The first three points of the triangular meshing are collinear |
| H_ERR_TRI_IDPNT | 9282 | Planar triangular meshing contains identical input points |
| H_ERR_TRI_IDPNTIN | 9283 | Invalid points for planar triangular meshing |
| H_ERR_TRI_NALLOC | 9284 | Internal error: allocated array too small for planar triangular meshing |
| H_ERR_TRI_ITRI | 9285 | Internal error: planar triangular meshing inconsistent |
| H_ERR_TRI_OUTR | 9286 | Node index outside triangulation range |
| H_ERR_TRI_LOCINC | 9290 | Local inconsistencies in all valid neighborhoods (parameters only allow few valid neighborhoods or point cloud not subsampled) |
| H_ERR_WSPVP | 9300 | Eye point and reference point coincide |
| H_ERR_DQ_ZERO_NORM | 9310 | Real part of the dual quaternion has length 0 |
| H_ERR_TIMEOUT | 9400 | Timeout occurred |
| H_ERR_WRONG_TIMEOUT | 9401 | Invalid value for timeout |

| Error Name | Code | Description |
|--|------|---|
| H_ERR_TIMEOUT_AFTER_SBM_CLEAR | 9402 | Timeout occurred after cached transformations have been freed (internal error) |
| H_ERR_DEFORM_WRONG_NUM_CLUSTER | 9450 | Invalid value for 'part_size' |
| H_ERR_DEFORM_WRONG_NUM_MIN_SIZE | 9451 | Invalid value for 'min_size' |
| H_ERR_DEFORM_WRONG_NUM_LSQ | 9452 | Invalid number of least-squares iterations |
| H_ERR_DEFORM_WRONG_ANGLE_STEP | 9453 | Invalid value for 'angle_step' |
| H_ERR_DEFORM_WRONG_SCALE_R_STEP | 9454 | Invalid value for 'scale_r_step' |
| H_ERR_DEFORM_WRONG_SCALE_C_STEP | 9455 | Invalid value for 'scale_c_step' |
| H_ERR_DEFORM_WRONG_MAX_ANGLE | 9456 | Invalid value for 'max_angle_distortion' |
| H_ERR_DEFORM_WRONG_MAX_ANISO | 9457 | Invalid value for 'max_aniso_scale_distortion' |
| H_ERR_DEFORM_WRONG_MIN_SIZE | 9458 | Invalid value for 'min_size' |
| H_ERR_DEFORM_WRONG_COV_POSE_MODE | 9459 | Invalid value for 'cov_pose_mode' |
| H_ERR_DEFORM_NO_CALIBRATION_INFO | 9460 | Model contains no calibration information |
| H_ERR_DEFORM_WRONG_PARAM_NAME | 9461 | Generic parameter name does not exist |
| H_ERR_DEFORM_IMAGE_TO_CAMERA_DIFF | 9462 | Provided camera parameters have different resolution than image |
| H_ERR_DEFORM_NO_MODEL_IN_FILE | 9463 | Invalid file format for deformable model |
| H_ERR_DEFORM_WRONG_VERSION | 9464 | The version of the deformable model is not supported |
| H_ERR_DEFORM_WRONG_SMOOTH_DEFORM | 9465 | Invalid 'deformation_smoothness' |
| H_ERR_DEFORM_WRONG_EXPAND_BORDER | 9466 | Invalid 'expand_border' |
| H_ERR_DEFORM_ORIGIN_OUTSIDE_TEMPLATE | 9467 | Model origin outside of axis-aligned bounding rectangle of template region |
| H_ERR_DEFORM_NOSITEM | 9468 | Serialized item does not contain a valid deformable model |
| H_ERR_VIEW_ESTIM_FAIL | 9499 | Estimation of viewpose failed |
| H_ERR_SFM_NO_POINTS | 9500 | 3D Object Model has no points |
| H_ERR_SFM_NO_FACES | 9501 | 3D Object Model has no faces |
| H_ERR_SFM_NO_NORMALS | 9502 | 3D Object Model has no normals |
| H_ERR_SFM_NO_VISIBILITY | 9503 | 3D surface model not trained for calculating view-based score |
| H_ERR_SFM_NO_3D_EDGES | 9504 | 3D surface model not trained for edge-supported matching |
| H_ERR_SFM_NO_SFM_FILE | 9506 | Invalid file format for 3D surface model |
| H_ERR_SFM_WRONG_FILE_VERSION | 9507 | The version of the 3D surface model is not supported |
| H_ERR_SFM_NOSITEM | 9508 | Serialized item does not contain a valid 3D surface model |
| H_ERR_SFM_TOO_MANY_SYMMS | 9509 | Given symmetry poses generate too many symmetric poses |
| H_ERR_OM3D_INVALID_FILE | 9510 | Invalid 3D file |
| H_ERR_OM3D_INVALID_MODEL | 9511 | Invalid 3D object model |
| H_ERR_OM3D_UNKNOWN_FILE_TYPE | 9512 | Unknown file type |
| H_ERR_OM3D_WRONG_FILE_VERSION | 9513 | The version of the 3D object model is not supported |
| H_ERR_OM3D_MISSING_ATTRIB | 9514 | Required attribute missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_V_COORD | 9515 | Required points missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_V_NORMALS | 9516 | Required normals missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_F_TRIANGLES | 9517 | Required triangulation missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_F_LINES | 9518 | Required polylines missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_F_TRINEIGB | 9519 | Required triangle neighborhood missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_F_POLYGONS | 9520 | Required polygons missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_V_2DMAP | 9521 | Required 2D mapping missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_O_PRIMITIVE | 9522 | Required primitive missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_SHAPE_MODEL | 9523 | Required 3D shape model missing in 3D object model |
| H_ERR_OM3D_MISSING_ATTRIB_EXTENDED | 9524 | Required extended attribute missing in 3D object model |
| H_ERR_OM3D_NOSITEM | 9525 | Serialized item does not contain a valid 3D object model |
| H_ERR_OM3D_MISSING_O_PRIMITIVE_EXTENSION | 9526 | Primitive in 3D object model has no extended data |
| H_ERR_OM3D_CONTAIN_ATTRIB_F_TRIANGLES | 9527 | Operation invalid, 3D object model already contains triangles |
| H_ERR_OM3D_CONTAIN_ATTRIB_F_LINES | 9528 | Operation invalid, 3D object model already contains lines |
| H_ERR_OM3D_CONTAIN_ATTRIB_F_POLYGONS | 9529 | Operation invalid, 3D object model already contains faces or polygons |
| H_ERR_OM3D_ISOLATED_OBJECT | 9530 | For at least one input 3D object model no neighbor with sufficient surface overlap is available |
| H_ERR_OM3D_SET_ALL_COORD | 9531 | All components of points must be set at once |

| Error Name | Code | Description |
|---------------------------------------|------|--|
| H_ERR_OM3D_SET_ALL_NORMALS | 9532 | All components of normals must be set at once |
| H_ERR_OM3D_NUM_NOT_FIT_COORD | 9533 | Number of values does not correspond to number of already existing points |
| H_ERR_OM3D_NUM_NOT_FIT_NORMALS | 9534 | Number of values does not correspond to number of already existing normals |
| H_ERR_OM3D_NUM_NOT_FIT_TRIANGLES | 9535 | Number of values does not correspond to already existing triangulation |
| H_ERR_OM3D_NUM_NOT_FIT_POLYGONS | 9536 | Number of values does not correspond to length of already existing polygons |
| H_ERR_OM3D_NUM_NOT_FIT_LINES | 9537 | Number of values does not correspond to length of already existing polylines |
| H_ERR_OM3D_NUM_NOT_FIT_2DMAP | 9538 | Number of values does not correspond to already existing 2D mapping |
| H_ERR_OM3D_NUM_NOT_FIT_EXTENDED | 9539 | Number of values does not correspond to already existing extended attribute |
| H_ERR_OM3D_FACE_INTENSITY_WITH_POINTS | 9540 | Per-face intensity is used with attribute 'points' |
| H_ERR_OM3D_ATTRIBUTE_NOT_SUPPORTED | 9541 | At least one attribute is not supported |
| H_ERR_OM3D_NOT_IN_BB | 9542 | No point within bounding box |
| H_ERR_DIF_TOO_SMALL | 9543 | distance_in_front is smaller than the 'Resolution' |
| H_ERR_MINTH_TOO_SMALL | 9544 | The minimum thickness is smaller than the surface tolerance |
| H_ERR_OM3D_WRONG_DIMENSION | 9545 | Input width or height does not match the number of points in 3D object model |
| H_ERR_OM3D_MISSING_DIMENSION | 9546 | Image width or height must be set to compute the XYZ-mapping |
| H_ERR_SF_OM3D_TRIANGLES_NOT_SUITABLE | 9550 | Triangles of the 3D object model are not suitable for this operator |
| H_ERR_SF_OM3D_FEW_POINTS | 9551 | Too few suitable 3D points in the 3D object model |
| H_ERR_NO_SERIALIZED_ITEM | 9580 | Invalid file format for serialized items |
| H_ERR_END_OF_FILE | 9581 | Serialized item: premature end of file |
| H_ERR_SID_WRONG_RESIZE_METHOD | 9600 | Invalid value for 'image_resize_method' |
| H_ERR_SID_WRONG_RESIZE_VALUE | 9601 | Invalid value for 'image_resize_value' |
| H_ERR_SID_WRONG_RATING_METHOD | 9602 | Invalid value for 'rating_method' |
| H_ERR_SID_NO_IMAGE_INFO_TYPE | 9603 | At least one type of image information must be added |
| H_ERR_SID_MODEL_NO_COLOR | 9604 | Sample identifier does not contain color information |
| H_ERR_SID_MODEL_NO_TEXTURE | 9605 | Sample identifier does not contain texture information |
| H_ERR_SID_NO_IMAGE_INFO | 9606 | Sample image does not contain enough information |
| H_ERR_SID_NO_UNPREPARED_DATA | 9607 | Sample identifier does not contain unprepared data (use add_sample_identifier_preparation_data) |
| H_ERR_SID_MODEL_NOT_PREPARED | 9608 | Sample identifier has not been prepared yet (use prepare_sample_identifier) |
| H_ERR_SID_NO_UNTRAINED_DATA | 9609 | Sample identifier does not contain untrained data (use add_sample_identifier_training_data) |
| H_ERR_SID_MODEL_NOT_TRAINED | 9610 | Sample identifier has not been trained yet (use train_sample_identifier) |
| H_ERR_SID_NO_RESULT_DATA | 9611 | Sample identifier does not contain result data |
| H_ERR_SID_NUM_TRAIN_OBJ | 9612 | Sample identifier must contain at least two training objects (use add_sample_identifier_training_data) |
| H_ERR_FINI_USR_THREADS | 9700 | More than one user thread still uses HALCON resources during finalization |
| H_ERR_NO_ENCRYPTED_ITEM | 9800 | Invalid file format for encrypted items |
| H_ERR_WRONG_PASSWORD | 9801 | Wrong password |
| H_ERR_ENCRYPT_FAILED | 9802 | Encryption failed |
| H_ERR_DECRYPT_FAILED | 9803 | Decryption failed |

Appendix B

HALCON Semantic Types

In the following, the HALCON semantic types are listed. For more information about semantic types, see [section 2.3.3](#) on page 29.

| | | | |
|--------------------------|-----------------------------|----------------------------|------------------------------------|
| angle | any | arc | attribute |
| barcode | barrier | bead_inspection_model | bg_estimation |
| calib_data | camera_setup_model | campar | chain |
| channel | chord | circle | circle_arc |
| circle_sector | class_box | class_gmm | class_knn |
| class_lut | class_mlp | class_svm | class_train_data |
| color_trans_lut | component_model | component_training | compute_device |
| condition | contour | coordinates | datacode_2d |
| deep_counting | deep_ocr | deformable_model | deformable_surface_matching_result |
| deformable_surface_model | descriptor_model | dev_tool | dict |
| distribution | dl_classifier | dl_classifier_result | dl_classifier_train_result |
| dl_device | dl_layer | dl_model | dl_pruning |
| drawing_object | dual_quaternion | ellipse | ellipse_arc |
| ellipse_sector | encrypted_item | event | exception |
| extent | feature_set | file | filename |
| framegrabber | function_1d | generic_shape_model_result | gnuplot |
| grayval | handle | hesseline | histogram |
| hom_mat2d | hom_mat3d | iline | image |
| info | integer | io_channel | io_device |
| lexicon | line | matrix | measure |
| memory_block | message | message_queue | metrology_model |
| mutex | ncc_model | number | object |
| object_model_3d | ocr_box | ocr_cnn | ocr_knn |
| ocr_mlp | ocr_svm | ocv | operator_set |
| point | point3d | pointer | polygon |
| pose | proc_name | quaternion | real |
| rectangle | rectangle2 | region | sample_identifier |
| scanner | scattered_data_interpolator | scene_3d | serial |
| serialized_item | shape_model | shape_model_3d | sheet_of_light_model |
| socket | stereo_model | string | structured_light_model |
| surface_matching_result | surface_model | system | template |
| text_model | text_result | texture_inspection_model | texture_inspection_result |
| thread_id | tuple | untyped_object | user |
| variation_model | window | xld | xld_cont |
| xld_dist_trans | xld_ext_para | xld_mod_para | xld_para |

Index

- abort_mode, [26](#)
- abstract, [21](#)
- accessing iconic objects, [57](#), [62](#)
- action procedure, [13](#), [16](#), [46](#)
- alternatives, [23](#)
- area of definition, [48](#)
- arrays, [40](#)
- assertion, [33](#), [34](#)
- attention, [23](#)

- border treatment, [83](#)
- buffer, [10](#)
- BYTE_IMAGE, [50](#), [70](#), [91](#)

- C, [14](#), [21](#), [27](#), [39](#), [98](#)
- C++, [14](#), [21](#), [23](#), [27](#), [98](#)
- C#, [14](#), [23](#), [27](#), [98](#)
- CB, [52](#), [84](#), [91](#), [93](#)
- CE, [52](#), [84](#), [91](#), [93](#)
- center of gravity, [88](#)
- channel, [61](#), [89](#)
- channels, [59](#), [89](#), [90](#)
- chapter, [22](#)
- chord, [50](#), [51](#)
- class of a parameter, [29](#)
- comments, [20](#)
- COMPLEX_IMAGE, [50](#)
- complexity, [27](#)
- constants
 - BYTE_IMAGE, [50](#), [70](#), [91](#)
 - COMPLEX_IMAGE, [50](#)
 - CYCLIC_IMAGE, [50](#)
 - DIR_IMAGE, [50](#)
 - FLOAT_IMAGE, [50](#), [70](#)
 - IMAGE1, [59](#)
 - IMAGE2, [59](#)
 - IMAGE_INDEX, [59](#), [69](#)
 - INT1_IMAGE, [50](#)
 - INT2_IMAGE, [50](#)
 - INT4_IMAGE, [50](#)
 - INT8_IMAGE, [50](#)
 - LONG_IMAGE, [50](#), [70](#)
 - LONG_PAR, [55](#), [72](#), [74–76](#), [79–81](#)
 - MAX_FORMAT, [48](#), [49](#)
 - REGION, [59](#)
 - STRING_PAR, [55](#), [72](#), [74–76](#), [79–81](#)
 - UINT2_IMAGE, [50](#)
 - VF_IMAGE, [50](#)
 - XLD_CONTOUR_ID, [62](#), [71](#)
 - XLD_POLYGON_ID, [62](#), [71](#)
- contour attributes, [52](#), [54](#)

- control parameters, [72](#)
- costs_weight, [31](#)
- CYCLIC_IMAGE, [50](#)

- data types, [49](#)
 - HComplexPixel, [51](#)
 - Hcont, [44](#), [53](#), [54](#), [62](#), [71](#)
 - Hcpar, [55](#), [72](#), [74](#), [76](#), [78–80](#), [88](#)
 - Herror (C), [46](#), [47](#), [83](#)
 - Himage, [43](#), [48](#), [50](#), [61](#), [64](#), [70](#), [87](#), [89](#)
 - HInt2Pixel, [51](#)
 - Hkey, [57](#), [60](#), [61](#)
 - Hobject (C), [10](#)
 - Hpar, [55](#)
 - HPixelImage, [50](#)
 - Hpoly, [53](#), [62](#), [71](#)
 - HRegFeature, [52](#)
 - Hrregion, [42](#), [51](#), [51](#), [52](#), [60](#), [62](#), [63](#), [69](#), [87](#)
 - Htuple (C), [10](#)
 - HUInt2Pixel, [51](#)
 - numeric types, [39](#)
- database key, [55](#), [57](#), [59–62](#), [64](#), [66–70](#)
- database of iconic objects, [9](#), [42](#), [43](#), [49](#), [51](#), [57](#), [62](#), [67–71](#)
- default_type, [15](#), [29](#)
- default_value, [32](#)
- definition file (DEF file), [14](#)
- description, [32](#)
- DIR_IMAGE, [50](#)
- directories
 - bin, [12](#)
 - def, [12](#)
 - doc, [12](#), [13](#)
 - examples, [12](#)
 - help, [12](#), [13](#)
 - images, [12](#)
 - include, [12](#)
 - lib, [12](#)
- domain, [59](#), [66](#), [68](#), [87–90](#)
- domain_concat_mult_inp, [26](#)
- domain_concat_si_inp, [26](#)
- DOUBLE_PAR, [55](#), [72](#), [74–76](#), [79–81](#)

- environment variables
 - HALCONEXAMPLES, [104](#)
 - HALCONEXTENSIONS, [9](#), [13](#), [100](#), [101](#), [103](#)
 - HALCONROOT, [104](#)
 - LD_LIBRARY_PATH, [14](#), [104](#)
- error codes, [47](#)
- error handling (HALCON)
 - error codes

- H_ERR_ICM, 45
- H_ERR_WIT, 48, 91
- H_ERR_XLD_CAND, 55
- H_MSG_OK, 46, 83
- H_MSG_TRUE, 10, 46
- etags, 98
- example, 27
- feature extraction, 48, 88
- file_ext, 35
- file_ext_descr, 35
- files
 - HCpackage.c, 100
 - HCpackage.h, 100
 - HCpackage.obj, 102
 - HCPPpackage.cpp, 101
 - HCPPpackage.h, 101
- filter, 48, 70, 83, 87, 90
- FLOAT_IMAGE, 50, 70
- functionality, 23
- global variables, 41
- graphics software, 9
- H_ERR_ICM, 45
- H_ERR_WIT, 48, 91
- H_ERR_XLD_CAND, 55
- H_MSG_OK, 46, 83
- H_MSG_TRUE, 10, 46
- HAddXLDContAttrib, 54
- HAddXLDContGlobalAttrib, 54
- HALCON, 41
- HALCON XL, 12
- HALCON/.NET, 10
- HALCON/C++, 10
- HALCONEXAMPLES, 104
- HALCONEXTENSIONS, 9, 13, 100, 101, 103
- HALCONROOT, 104
- HAllComp, 65, 66, 89, 90
- HAllFilter, 87, 88, 90, 92, 95
- HAllFilter2, 87, 88, 92
- HAllObj, 59, 62, 65, 66, 66, 71, 88–90
- HAllloc, 43, 44, 44, 45, 71, 75, 79–82
- HAlllocLocal, 42, 43, 45, 75
- HAlllocOutputHandle, 43
- HAlllocRL, 45
- HAlllocRLLocal, 42, 43
- HAlllocRLNum, 45
- HAlllocRLNumLocal, 42
- HAlllocRLNumTmp, 41, 51, 84
- HAlllocRLTmp, 41, 42, 51, 61–64, 85, 90, 92–94
- HAlllocStringMem, 77, 78, 79, 80
- HAlllocTmp, 41, 45, 75, 80
- HAlllocXLDCont, 44, 72
- HAllReg, 87, 88, 88, 89, 94, 95
- HAllSegm, 16, 87, 88, 89, 91
- HANDLE_PAR, 55, 72
- HBase.h, 49
- HCKNoObj, 82, 83
- HCKP, 16, 47, 57, 59–66, 68–72, 74, 76–82, 83, 84, 85, 89–91, 93–95
- HCol, 49
- hcomp, 15, 97
- HComplexPixel, 51
- Hcont, 44, 53, 54, 62, 71
- HCopyElemD, 76, 77, 78
- HCopyElemL, 76, 77, 78
- HCopyObj, 67, 68, 69, 71, 90, 94
- HCopyXLDCont, 54
- HCopyXLDContPart, 54
- Hcpar, 55, 72, 74, 76, 78–80, 88
- HCrImage, 66–68, 70
- HCrObj, 66, 67, 67, 69, 70, 94, 95
- HCrXLD, 68, 71
- HDefObj, 66–69, 69, 70, 71
- HDevelop, 14–16, 22, 23, 98
- HDFImage, 91, 92, 92, 93
- HDoLowError, 45
- HDOTNETpackage.cs, 98, 101, 102
- HDupObj, 93, 94
- help files, 16, 35, 98
- Herror, 46, 47, 83
- HErrorDef.h, 47
- HFree, 44, 75
- HFreeAllTmp, 41
- HFreeLocal, 42, 75
- HFreeNTmp, 41
- HFreeRL, 45
- HFreeRLLocal, 42
- HFreeRLTmp, 41, 61–64, 84, 90, 92–94
- HFreeTmp, 41, 75
- HFreeUpToTmp, 41, 85
- HFreeXLDCont, 44
- HGetCElemH, 72, 76
- HGetCElemH1, 72, 76
- HGetCElemH1, HGetCElemH, HGetCElemHN, 75
- HGetCElemHN, 72, 76
- HGetComp, 58, 59, 61, 62, 64, 71
- HGetCPar, 16, 72, 72, 74, 76, 77, 78
- HGetCParNum, 77
- HGetDImage, 63, 64, 64, 66
- HGetDRL, 62, 63
- HGetElemD, 72, 77
- HGetElemL, 72, 77
- HGetElemL, HGetElemD, HGetElemS, 75
- HGetElemS, 72, 77
- HGetFDRL, 60, 62, 63, 66, 69, 71, 88–90
- HGetImage, 58, 60, 61, 64, 71
- HGetObj, 57, 58, 60–63, 65, 66, 69, 94
- HGetObjNum, 59, 63, 65, 65
- HGetPElem, 72, 73, 74, 77
- HGetPElemD, 72, 73
- HGetPElemL, 72, 73
- HGetPElemS, 72, 73
- HGetPPar, 72, 73, 74, 77
- HGetRL, 58, 60, 61, 62
- HGetSPar, 64, 71, 77, 80, 91, 95
- HGetURL, 62, 63, 63, 85

- HGetXLD, [58](#), [62](#)
- Himage, [43](#), [48](#), [50](#), [61](#), [64](#), [70](#), [87](#), [89](#)
- HImageFD, [91](#), [92](#), [92](#), [93](#)
- HIIncrRL, [84](#)
- HInt2Pixel, [51](#)
- Hkey, [57](#), [60](#), [61](#)
- HLinCoor, [49](#), [61](#), [64](#)
- HLookupXLDContAttrib, [54](#)
- HLookupXLDContGlobalAttrib, [54](#)
- HMEMglobal, [75](#)
- HMEMlocal, [75](#)
- HMEMtemp, [75](#)
- HNewImage, [44](#), [95](#)
- HNewImagePtr, [44](#)
- HNewRegion, [16](#), [88](#), [90](#), [93](#), [94](#), [95](#)
- HNumOfChannels, [60](#), [82](#), [84](#), [89](#)
- Hobject, [10](#)
- Hpackage.c, [98](#), [100](#)
- Hpar, [55](#)
- HPGetURL, [85](#)
- HPixelImage, [50](#)
- HPNumOfChannels, [59](#), [60](#), [84](#)
- Hpoly, [53](#), [62](#), [71](#)
- HPutCPar, [62](#), [64](#), [72](#), [79](#), [80](#), [81](#), [88](#), [89](#)
- HPutDImage, [68](#), [70](#), [90](#), [95](#)
- HPutDRL, [67–69](#), [69](#), [70](#)
- HPutElem, [72](#), [80](#), [81](#)
- HPutElemH, [72](#), [80](#)
- HPutImage, [44](#), [67–69](#), [69](#), [70](#)
- HPutPElem, [72](#), [79](#), [81](#)
- HPutPPar, [72](#), [79](#), [81](#)
- HPutRect, [68](#), [93](#), [94](#)
- HReadGV, [43](#), [59](#)
- HReadGVA, [59](#), [59](#), [65](#), [69](#)
- HRealloc, [44](#)
- HReallocLocal, [42](#)
- HReallocRLNum, [45](#)
- HReallocRLNumLocal, [42](#)
- HRegFeature, [52](#)
- HRLArea, [88](#)
- HRLDecomp, [82](#), [83](#), [83](#)
- Hrlregion, [42](#), [51](#), [51](#), [52](#), [60](#), [62](#), [63](#), [69](#), [87](#)
- HRow, [49](#)
- HSetErrText, [47](#)
- HTestAllTmp, [45](#)
- HTestMem, [45](#)
- HTestPtr, [45](#)
- HTestTmp, [45](#)
- HTML reference, [13](#)
- Htuple, [10](#)
- HUInt2Pixel, [51](#)
- HVFPixel, [51](#)
- HWriteGV, [43](#)
- HXLDFreeContour, [71](#)
- HXLDFreePolygon, [72](#)

- iconic object key, [10](#)
- image component, [59](#)
- image components, [67](#)
- image matrix, [49](#), [59](#), [69](#), [70](#)
- image processing hardware, [9](#)
- image size, [49](#), [90](#)
- image vector, [49](#)
- IMAGE1, [59](#)
- IMAGE2, [59](#)
- IMAGE_INDEX, [59](#), [69](#)
- images, [49](#)
- include files (HALCON)
 - HBase.h, [49](#)
 - IPType.h, [49](#)
- index, [59](#), [87](#)
- input control parameter, [72](#), [74–76](#), [91](#)
- INT1_IMAGE, [50](#)
- INT2_IMAGE, [50](#)
- INT4_IMAGE, [50](#)
- INT8_IMAGE, [50](#)
- IPType.h, [49](#)

- keywords, [23](#)

- LD_LIBRARY_PATH, [14](#), [104](#)
- linear coordinate, [49](#)
- Linux, [11](#), [14](#), [103](#)
- local variables, [40](#)
- LONG_IMAGE, [50](#), [70](#)
- LONG_PAR, [55](#), [72](#), [74–76](#), [79–81](#)

- MAX_FORMAT, [48](#), [49](#)
- memory costs, [95](#)
- memory management, [41](#)
- method, [25](#)
- MIXED_PAR, [72](#), [74](#)
- modified, [30](#)
- module, [22](#)
- multi-channel image, [49](#)
- multichannel, [10](#), [34](#)
- multiinstance, [35](#)
- multivalued, [10](#), [30](#)
- multivalued, [35](#)

- Name, [28](#)

- operator description, [19](#)
 - abstract, [21](#)
 - alternatives, [23](#)
 - assertion, [33](#), [34](#)
 - attention, [23](#)
 - chapter, [22](#)
 - complexity, [27](#)
 - costs_weight, [31](#)
 - default_type, [15](#), [29](#)
 - default_value, [32](#)
 - description, [32](#)
 - example, [27](#)
 - file_ext, [35](#)
 - file_ext_descr, [35](#)
 - functionality, [23](#)
 - keywords, [23](#)
 - languages, [20](#)
 - method, [25](#)
 - module, [22](#)

- multichannel, 10, **34**
- multivalue, 10, **30**
- Name, **28**
- parallelization, **24**
- postprocessing, **31**
- predecessor, **23**
- process_exclusively, **24**
- process_locally, **25**
- process_mutual, **25**
- references, **27**
- region_postprocessing, **25**
- result_state, **24**
- see_also, **23**
- sem_type, 15, **29, 32**
- short, **21**
- step_min, **33**
- step_rec, **33**
- successor, **23**
- type_list, **32**
- value_function, **33**
- value_list, **33**
- value_max, **33**
- value_min, **33**
- value_number, **33**
- values, **33**
- operators_en_US.idx, 98
- operators_en_US.key, 98
- operators_en_US.num, 98
- operators_en_US.ref, 98
- operators_en_US.sta, 98
- OpRef, **36**
- origin of an image, 49
- output iconic parameter, 67
- output image, 90
- package, 11
 - action procedure, 13, 16, 46
 - directories
 - bin, 12
 - def, 12
 - doc, 12, 13
 - examples, 12
 - help, 12, 13
 - images, 12
 - include, 12
 - lib, 12
 - files
 - definition file, 14
 - HCpackage.c, 100
 - HCpackage.h, 100
 - HCpackage.obj, 102
 - HCPPpackage.cpp, 101
 - HCPPpackage.h, 101
 - help files, 16, 35, 98
 - reference manual
 - HTML, 98
 - OpRef, 36
 - ParRef, 36
 - PDF, 99
 - ValRef, 36
 - supply procedure, 13, 15, 16, 46, 87, 90, 98
- parallelization, **24**
- parameter classes, 19, 21
- Parameters, 40
- ParRef, 36
- pixel data, 49, 87
- pixel type, 48, 49, 70, 90
- pixel types, 49, 89
- postprocessing, **31**
- predecessor, **23**
- procedure handle, 10
- procedure names, 46
- procedures/macros
 - accessing control parameters
 - HAllocStringMem, 77, **78, 79, 80**
 - HGetCPar, 16, 72, **72, 74, 76, 77, 78**
 - HGetCParNum, 77
 - HGetPPar, **72, 73, 74, 77**
 - HGetSPar, 64, 71, **77, 80, 91, 95**
 - HPutCPar, 62, 64, **72, 79, 80, 81, 88, 89**
 - HPutPPar, **72, 79, 81**
 - accessing iconic objects
 - CB, **52, 84, 91, 93**
 - CE, **52, 84, 91, 93**
 - HAddXLDContAttrib, **54**
 - HAddXLDContGlobalAttrib, **54**
 - HCkNoObj, **82, 83**
 - HCol, **49**
 - HCopyObj, 67, **68, 69, 71, 90, 94**
 - HCopyXLDCont, **54**
 - HCopyXLDContPart, **54**
 - HCrImage, 66–68, **70**
 - HCrObj, 66, 67, **67, 69, 70, 94, 95**
 - HCrXLD, 68, **71**
 - HDefObj, 66–69, **69, 70, 71**
 - HDFImage, 91, 92, **92, 93**
 - HDupObj, 93, **94**
 - HGetComp, 58, **59, 61, 62, 64, 71**
 - HGetDImage, 63, 64, **64, 66**
 - HGetDRL, **62, 63**
 - HGetFDRL, 60, **62, 63, 66, 69, 71, 88–90**
 - HGetImage, 58, 60, **61, 64, 71**
 - HGetObj, **57, 58, 60–63, 65, 66, 69, 94**
 - HGetObjNum, 59, 63, 65, **65**
 - HGetRL, 58, **60, 61, 62**
 - HGetURL, 62, 63, **63, 85**
 - HGetXLD, 58, **62**
 - HImageFD, 91, 92, **92, 93**
 - HLinCoor, **49, 61, 64**
 - HLookupXLDContAttrib, **54**
 - HLookupXLDContGlobalAttrib, **54**
 - HNewRegion, 16, 88, 90, 93, **94, 95**
 - HNumOfChannels, 60, 82, **84, 89**
 - HPNumOfChannels, 59, **60, 84**
 - HPutDImage, 68, **70, 90, 95**
 - HPutDRL, 67–69, **69, 70**
 - HPutImage, 44, 67–69, **69, 70**
 - HPutRect, 68, 93, **94**
 - HRow, **49**

- basic
 - HCKP, 16, 47, 57, 59–66, 68–72, 74, 76–82, 83, 84, 85, 89–91, 93–95
 - HDoLowError, 45
 - HReadGV, 43, 59
 - HReadGVA, 59, 59, 65, 69
 - HRLDecomp, 82, 83, 83
 - HSetErrText, 47
 - HWriteGV, 43
- loop macros
 - HAllComp, 65, 66, 89, 90
 - HAllFilter, 87, 88, 90, 92, 95
 - HAllFilter2, 87, 88, 92
 - HAllObj, 59, 62, 65, 66, 66, 71, 88–90
 - HAllReg, 87, 88, 88, 89, 94, 95
 - HAllSegm, 16, 87, 88, 89, 91
- memory management
 - HAlloc, 43, 44, 44, 45, 71, 75, 79–82
 - HAllocLocal, 42, 43, 45, 75
 - HAllocRL, 45
 - HAllocRLLocal, 42, 43
 - HAllocRLNum, 45
 - HAllocRLNumLocal, 42
 - HAllocRLNumTmp, 41, 51, 84
 - HAllocRLTmp, 41, 42, 51, 61–64, 85, 90, 92–94
 - HAllocTmp, 41, 45, 75, 80
 - HAllocXLDCont, 44, 72
 - HFree, 44, 75
 - HFreeAllTmp, 41
 - HFreeLocal, 42, 75
 - HFreeNTmp, 41
 - HFreeRL, 45
 - HFreeRLLocal, 42
 - HFreeRLTmp, 41, 61–64, 84, 90, 92–94
 - HFreeTmp, 41, 75
 - HFreeUpToTmp, 41, 85
 - HFreeXLDCont, 44
 - HNewImage, 44, 95
 - HNewImagePtr, 44
 - HRealloc, 44
 - HReallocLocal, 42
 - HReallocRLNum, 45
 - HReallocRLNumLocal, 42
 - HTestAllTmp, 45
 - HTestMem, 45
 - HTestPtr, 45
 - HTestTmp, 45
 - HXLDFreeContour, 71
 - HXLDFreePolygon, 72
- process_exclusively, 24
- process_locally, 25
- process_mutual, 25
- reference manual
 - HTML, 98
 - OpRef, 36
 - ParRef, 36
 - PDF, 99
 - ValRef, 36
- references, 27
- REGION, 59
- region, 62
- region data, 50
- region shape features, 51, 52
- region transformation, 94
- region_postprocessing, 25
- result_state, 24
- runlength encoding, 60, 62
- see_also, 23
- segmentation, 48, 87, 89, 90, 94
- sem_type, 15, 29, 32
- semantic type, 29
- short, 21
- size, 70, 89
- split_channel, 25
- split_domain, 25
- split_partial, 25
- split_partial_domain, 25
- split_tuple, 25
- static, 41
- step_min, 33
- step_rec, 33
- STRING_PAR, 55, 72, 74–76, 79–81
- successor, 23
- supply procedure, 13, 15, 16, 46, 87, 90, 98
- tuples, 88
- type_list, 32
- UINT2_IMAGE, 50
- union, 63
- user_thresh, 14, 15
- ValRef, 36
- value_function, 33
- value_list, 33
- value_max, 33
- value_min, 33
- value_number, 33
- values, 33
- VF_IMAGE, 50
- warning, 21
- Windows, 11, 14, 101
- XLD, 58, 68, 71, 94
- XLD_CONTOUR_ID, 62, 71
- XLD_POLYGON_ID, 62, 71
- XLDs, 9, 29, 52